

---

Subject: Re: Howto install vzyum using debian sarge host-node

Posted by [foxxfiles](#) on Tue, 01 Aug 2006 23:17:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi

I Try linking /etc/vz/vz.conf to /etc/sysconfig/vz (on the config file exist all variables need) But dont work.

```
host-node:/home/fox# ln -s /etc/vz/vz.conf /etc/sysconfig/vz
host-node:/home/fox# vzyum 106 install apache
ERROR: No such OS template: install
host-node:/home/fox#
```

conf dir

```
-----
host-node:/home/fox# ls /etc/vz/conf
0.conf  104.conf 108.conf 112.conf      116.conf.destroyed
101.conf 105.conf 109.conf 113.conf      ve-light.conf-sample
102.conf 106.conf 110.conf 114.conf      ve-vps.basic.conf-sample
103.conf 107.conf 111.conf 115.conf.destroyed
host-node:/home/fox# cat /etc/vz/
-----
```

vz.conf file

```
-----
## Global parameters
#
VIRTUOZZO=yes
LOCKDIR=/var/lib/vz/lock
DUMPDIR=/var/lib/vz/dump
VE0CPUUNITS=1000

## Logging parameters
#
LOGGING=yes
LOGFILE=/var/log/vzctl.log
LOG_LEVEL=0

## Disk quota parameters
#
DISK_QUOTA=yes
VZFASTBOOT=no

# The name of the device whose ip address will be used as source ip for VE.
# By default automatically assigned.
```

```
#VE_ROUTE_SRC_DEV="eth0"
```

```
## Template parameters
```

```
#
```

```
TEMPLATE=/var/lib/vz/template
```

```
## Defaults for VEs
```

```
#
```

```
VE_ROOT=/var/lib/vz/root/$VEID
```

```
VE_PRIVATE=/var/lib/vz/private/$VEID
```

```
CONFIGFILE="vps.basic"
```

```
DEF_OSTEMPLATE="debian-3.1-i386-minimal"
```

```
## Load vzwdog module
```

```
#
```

```
VZWDOG="no"
```

```
## Load ipTables Modules
```

```
#
```

```
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mang  
le ipt_TCPMSS ipt_tcpmss ipt_ttl ipt_length"
```

```
# EOF
```

```
-----
```

Fernando

---