
Subject: Re: Using PPP in a Virtual Server
Posted by [eroux](#) on Thu, 17 Aug 2006 14:30:39 GMT
[View Forum Message](#) <> [Reply to Message](#)

[root@vs01-vc01 ~]# cat /proc/1/status

Name: init
State: S (sleeping)
SleepAVG: 88%
Tgid: 1
Pid: 1
PPid: 0
TracerPid: 0
FNid: 42
Uid: 0 0 0 0
Gid: 0 0 0 0
FDSize: 32
Groups: 0 1 2 3 4 6 10
envID: 42
VPid: 1
PNState: 0
StopState: 0
VmPeak: 2008 kB
VmSize: 1996 kB
VmLck: 0 kB
VmHWM: 672 kB
VmRSS: 672 kB
VmData: 196 kB
VmStk: 88 kB
VmExe: 32 kB
VmLib: 1632 kB
VmPTE: 40 kB
StaBrk: 08051000 kB
Brk: 088a2000 kB
StaStk: bffcdeb0 kB
ExecLim: 08050000
Threads: 1
SigQ: 0/8052
SigPnd: 0000000000000000
ShdPnd: 0000000000000000
SigBlk: 0000000000000000
SigIgn: ffffffff57f0d8fc
SigCgt: 00000000280b2603
SigSvd: 0000000000000000
CapInh: 000000005ffffeff
CapPrm: 000000005ffffeff
CapEff: 000000005ffffeff
Cpus_allowed: ffffffff
Mems_allowed: 1

TaskUB: 42
MMUB: 42
[root@vs01-vc01 ~]#

No go even with:

```
/etc/vz/conf/42.confCAPABILITY="CHOWN:on DAC_OVERRIDE:on DAC_READ_SEARCH:on  
FOWNER:on FSETID:on KILL:on SETGID:on SETUID:on LINUX_IMMUTABLE:on  
NET_BIND_SERVICE:on NET_BROADCAST:on NET_ADMIN:on NET_RAW:on IPC_LOCK:on  
IPC_OWNER:on SYS_MODULE:on SYS_RAWIO:on SYS_CHROOT:on SYS_PTRACE:on  
SYS_PACCT:on SYS_ADMIN:on SYS_BOOT:on SYS_NICE:on SYS_RESOURCE:on  
SYS_TIME:on SYS_TTY_CONFIG:on MKNOD:on LEASE:on"
```

So I don't know...
