

---

Subject: Re: smtp port

Posted by [youp](#) on Wed, 06 Sep 2006 07:38:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

on vps :

```
strace -f -e trace=file telnet 69.64.46.7 25
execve("/usr/bin/telnet", ["telnet", "69.64.46.7", "25"], [/* 17 vars */]) = 0
access("/etc/ld.so.preload", R_OK) = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY) = 3
open("/lib/libutil.so.1", O_RDONLY) = 3
open("/usr/lib/libncurses.so.5", O_RDONLY) = 3
open("/lib/libc.so.6", O_RDONLY) = 3
open("/lib/libdl.so.2", O_RDONLY) = 3
Trying 69.64.46.7...
```

```
-bash-3.00# strace -f -e trace=file telnet 69.64.46.7 80
execve("/usr/bin/telnet", ["telnet", "69.64.46.7", "80"], [/* 17 vars */]) = 0
access("/etc/ld.so.preload", R_OK) = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY) = 3
open("/lib/libutil.so.1", O_RDONLY) = 3
open("/usr/lib/libncurses.so.5", O_RDONLY) = 3
open("/lib/libc.so.6", O_RDONLY) = 3
open("/lib/libdl.so.2", O_RDONLY) = 3
Trying 69.64.46.7...
open("../.telnetrc", O_RDONLY) = -1 ENOENT (No such file or directory)
Connected to 69.64.46.7.
Escape character is '^]'.
^]
telnet> quit
```

ON HW :

```
strace -f -e trace=file telnet 69.64.46.7 25
execve("/usr/bin/telnet", ["telnet", "69.64.46.7", "25"], [/* 29 vars */]) = 0
open("/etc/ld.so.preload", O_RDONLY) = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=27378, ...}) = 0
open("/lib/libutil.so.1", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=14100, ...}) = 0
open("/usr/lib/libncurses.so.5", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=2743560, ...}) = 0
open("/lib/tls/libc.so.6", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=1579688, ...}) = 0
open("/usr/lib/libgpm.so.1", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=20624, ...}) = 0
open("/lib/tls/libm.so.6", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=213192, ...}) = 0
```

```
open("/etc/nsswitch.conf", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=1695, ...}) = 0
open("/etc/ld.so.cache", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=27378, ...}) = 0
open("/lib/libnss_files.so.2", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=51136, ...}) = 0
open("/etc/resolv.conf", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=110, ...}) = 0
open("/etc/host.conf", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=17, ...}) = 0
open("/etc/hosts", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=186, ...}) = 0
open("/etc/ld.so.cache", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=27378, ...}) = 0
open("/lib/libnss_dns.so.2", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=18244, ...}) = 0
open("/lib/libresolv.so.2", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0755, st_size=73932, ...}) = 0
fstat64(1, {st_mode=S_IFCHR|0620, st_rdev=makedev(3, 1), ...}) = 0
Trying 69.64.46.7...
open("/root/.telnetrc", O_RDONLY) = -1 ENOENT (No such file or directory)
Connected to 69.64.46.7.
Escape character is '^]'.
220 vzorg.swsoft.net ESMTP Sendmail 8.13.1/8.13.1; Wed, 6 Sep 2006 03:36:45 -0400
```

i don't know if telnet are the same ...

---