Subject: Re: [PATCH, try3, 0/3] Separate logfile and console loglevel Posted by kfh on Thu, 07 Dec 2006 10:42:25 GMT View Forum Message <> Reply to Message

On Thursday den 7. December 2006 09:45, Igor Sukhih wrote:

> > Separate logfile and console loglevel

> > The separation is implemented as follows

>>

- >> 1: split --verbose from LOG_LEVEL
- >> verbose and LOG_LEVEL are both 0 as default
- >> --verbose will not affect LOG_LEVEL and vice versa

>

> Is standard command line syntax supported --verbose[=]<id> ? No. Will fix.

= is requied for <id>

- > > 2: Make --verbose accept optional value. Add VERBOSE to vz.conf
- >> VERBOSE=0 as default
- >> --verbose[=value]
- >> Increase or set the logging level.
- >> No arguments will increase the current value by one.

>

- > I don't like introducing the VERBOSE parameter. Why do you need so
- > complex setup LOG_LEVEL, VERBOSE, --verbose?
- > If you need to limit console verbosity use --verbose <id> command line

> option, by default console_level = log_level.

I would like more info in the logfile and a more quiet console.

To do that it is necessary to set LOG_LEVEL to 1 and then use --verbose=0 each time I invoke vzctl.

I think it is more complex :-)

> > 3: Make verbose=0 more quiet

- >> Raise default LOG_LEVEL to 2 and VERBOSE to 1
- >> Raise some logger(0, ...)
- >> No logger() above 3

>

> I don't see the reason to change default LOG_LEVEL, level > 0 usually

> used for debug, all

I think level 0 is used for "debug" today.

When starting a VE using LOG_LEVEL=0, I get 10 lines of output.

I think "Running VE script: /etc/vz/dists/..." is debug.

The only(?) way I see to make level 0 more quiet is to raise "noise" [0] to level 1 (and "Running VE script: ..." to level 2). If LOG_LEVEL is raised to 1 the output should be the same as today level 0. (Except "Running VE script: ...") --quiet is to quiet.

[0] "Noise" when starting VE using level 0: Setting CPU limit: 50
Setting CPU units: 1000
Configure meminfo: 10240
2 * "Running VE script: /etc/vz/dists/..."

> error messages are not controlled by --verbose, LOG_LEVEL and will be

> displayed any way.

> So if we only introduce --verbose <id> command line option is it not

> enough for you?

No, only if "noise" is moved to level 1.

> --

Igor./Kristian.

Page 2 of 2 ---- Generated from OpenVZ Forum