
Subject: RE: vzctl start id "VE start in progress", vzctl status"VEID exist mounted down"

Posted by [Stephen Fletcher](#) on Wed, 24 Jan 2007 05:24:34 GMT

[View Forum Message](#) <> [Reply to Message](#)

Dmesg has theese two line as its last entry

[129.091000] VPS: 777: started

[132.285000] VPS: 777: stopped

-----Original Message-----

From: users-bounces@openvz.org [mailto:users-bounces@openvz.org] On Behalf Of Kirill Korotaev

Sent: Tuesday, 23 January 2007 11:19 PM

To: users@openvz.org

Subject: Re: [Users] vzctl start id "VE start in progress", vzctl status"VEID exist mounted down", vzctl enter "VE is not running"

Stephen,

Is there anything in dmesg?

Thanks,

Kirill

> vzctl version 3.0.14

>

> root@stephens:~# uname -a

> Linux stephens 2.6.18-028test010 #2 PREEMPT Thu Jan 11 18:20:08 EST

> 2007

> i686 GNU/Linux

> root@stephens:~# cat /proc/vz/*

> Version: 2.7

> 0 b 016 *.*

> 0 c 006 *.*

> 0 0 77

> Version: 2.5

> Version: 2.2

>

> VEID user nice system uptime

idle

> strv uptime used maxlat

> totlat numsched

> Version: 1.0

> cat: /proc/vz/vzaquota: Is a directory

> qid: path usage softlimit hardlimit time

> expire

> 777: /vz/private/777

> 1k-blocks 198888 1048576 1153434 0

```

> 0
> inodes      11473      200000      220000      0
> 0
> root@stephens:~# lsmod | grep vz
> vznetdev      16928  1
> vzethdev      10764  0
> vxdquota      41748  1 [permanent]
> vzmon         41988  2 vznetdev,vzethdev
> vzdev         3972   4 vznetdev,vzethdev,vxdquota,vzmon
> ipv6         279776  15 vzmon
>
> root@stephens:~# vzctl start 777
> Starting VE ...
> VE is mounted
> Adding IP address(es): 192.168.99.2
> Setting CPU units: 1000
> VE start in progress...
> root@stephens:~# vzctl status
> VE id is not given
> root@stephens:~# vzctl status 777
> VEID 777 exist mounted down
> root@stephens:~# vzctl enter 777
> VE is not running
> root@stephens:~# vzctl restore 777
> Restoring VE ...
> Error: No checkpointing support, unable to open /proc/rst: No such
> file or directory root@stephens:~# ifconfig venet0
> venet0   Link encap:UNSPEC  HWaddr
> 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
>      UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
>      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
>      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
>      collisions:0 txqueuelen:0
>      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b) root@stephens:~# ip
> route
> <ethernet0ip>/27 dev eth0  proto kernel  scope link  src <ethernet0ip>
> default via <localgwip> dev eth0
>
> Help? :)
>

```
