
Subject: RE: vzctl start id "VE start in progress", vzctl status"VEID exist mounted down&quo

Posted by [Stephen Fletcher](#) on Sun, 28 Jan 2007 01:52:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

Dmesg has these two line as its last entry

```
[ 129.091000] VPS: 777: started
```

```
[ 132.285000] VPS: 777: stopped
```

-----Original Message-----

From: users-bounces@openvz.org [mailto:users-bounces@openvz.org] On Behalf Of Kirill Korotaev

Sent: Tuesday, 23 January 2007 11:19 PM

To: users@openvz.org

Subject: Re: [Users] vzctl start id "VE start in progress", vzctl status"VEID exist mounted down", vzctl enter "VE is not running"

Stephen,

Is there anything in dmesg?

Thanks,

Kirill

```
> vzctl version 3.0.14
```

```
>
```

```
> root@stephens:~# uname -a
```

```
> Linux stephens 2.6.18-028test010 #2 PREEMPT Thu Jan 11 18:20:08 EST
```

```
> 2007
```

```
> i686 GNU/Linux
```

```
> root@stephens:~# cat /proc/vz/*
```

```
> Version: 2.7
```

```
> 0 b 016 *.*
```

```
> 0 c 006 *.*
```

```
> 0 0 77
```

```
> Version: 2.5
```

```
> Version: 2.2
```

```
>
```

```
> VEID user nice system uptime
```

```
idle
```

```
> strv uptime used maxlat
```

```
> totlat numsched
```

```
> Version: 1.0
```

```
> cat: /proc/vz/vzaquota: Is a directory
```

```
> qid: path usage softlimit hardlimit time
```

```
> expire
```

```
> 777: /vz/private/777
```

```
> 1k-blocks 198888 1048576 1153434 0
```

```
> 0
> inodes      11473      200000      220000      0
> 0
> root@stephens:~# lsmod | grep vz
> vznetdev    16928 1
> vzetdev     10764 0
> vzdquota    41748 1 [permanent]
> vzmon       41988 2 vznetdev,vzetdev
> vzdev       3972 4 vznetdev,vzetdev,vzdquota,vzmon
> ipv6        279776 15 vzmon
>
> root@stephens:~# vzctl start 777
> Starting VE ...
> VE is mounted
> Adding IP address(es): 192.168.99.2
> Setting CPU units: 1000
> VE start in progress...
> root@stephens:~# vzctl status
> VE id is not given
> root@stephens:~# vzctl status 777
> VEID 777 exist mounted down
> root@stephens:~# vzctl enter 777
> VE is not running
> root@stephens:~# vzctl restore 777
> Restoring VE ...
> Error: No checkpointing support, unable to open /proc/rst: No such
> file or directory root@stephens:~# ifconfig venet0
> venet0  Link encap:UNSPEC HWaddr
> 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
>      UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
>      RX packets:0 errors:0 dropped:0 overruns:0 frame:0
>      TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
>      collisions:0 txqueuelen:0
>      RX bytes:0 (0.0 b) TX bytes:0 (0.0 b) root@stephens:~# ip
> route
> <ethernet0ip>/27 dev eth0 proto kernel scope link src <ethernet0ip>
> default via <localgwip> dev eth0
>
> Help? :)
>
```
