
Subject: [PATCH 3/4] add initlog feature to manual page
Posted by [dietmar](#) on Tue, 20 Sep 2011 05:17:17 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Dietmar Maurer <dietmar@proxmox.com>

Signed-off-by: Dietmar Maurer <dietmar@proxmox.com>

man/ctid.conf.5 | 5 +++++
1 files changed, 5 insertions(+), 0 deletions(-)

```
diff --git a/man/ctid.conf.5 b/man/ctid.conf.5
index d3ec3d0..ecda4ae 100644
--- a/man/ctid.conf.5
+++ b/man/ctid.conf.5
@@ -30,6 +30,11 @@ Specifies whether this container will be started during system boot.
Default is \fBno\fR, meaning the container will not be started
if \fBBONBOOT\fR parameter is omitted.
Corresponds to the \fB--onboot\fR option.
+.IP \fBINITLOG\fR="\fByes\fR|\fBno\fR"
+If enabled init output is logged to /var/log/init.log. An additional process started
+inside the container (init-logger) reads the output from init and writes it
+to /var/log/init.log.
+Corresponds to the \fB--initlog\fR option.
.IP \fBBOOTORDER\fR="\fInumber\fR"
Specifies the CT boot order priority. Corresponds to the
\fB--bootorder\fR option.
--
1.5.6.5
```

Subject: [PATCH 4/4] add INITLOG option to vz.conf
Posted by [dietmar](#) on Tue, 20 Sep 2011 05:17:18 GMT
[View Forum Message](#) <> [Reply to Message](#)

From: Dietmar Maurer <dietmar@proxmox.com>

Signed-off-by: Dietmar Maurer <dietmar@proxmox.com>

etc/vz.conf | 3 +++
1 files changed, 3 insertions(+), 0 deletions(-)

```
diff --git a/etc/vz.conf b/etc/vz.conf
index 63e509a..7f4d857 100644
--- a/etc/vz.conf
+++ b/etc/vz.conf
```

```
@@ -10,6 +10,9 @@ LOGFILE=/var/log/vzctl.log
LOG_LEVEL=0
VERBOSE=0
```

```
+## log output of init process to $VE_ROOT/var/log/init.log
+INITLOG=no
```

```
+
```

```
## Disk quota parameters
```

```
DISK_QUOTA=yes
```

```
VZFASTBOOT=no
```

```
--
```

```
1.5.6.5
```
