
Subject: Openafs in guests

Posted by [hlmayer](#) on Fri, 27 Apr 2012 10:40:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

My kernel: 2.6.32-042stab053.5

afs on the host: openafs-kernel-source-1.6.0-97.z2.sl6.x86_64

manually compiled

Packages installed (host)

openafs-krb5-1.6.0-93.pre4.sl6.x86_64

kmmod-openafs-1.6.0-97.z2.sl6.71.x86_64

openafs-1.6.0-93.pre4.sl6.x86_64

openafs-kernel-source-1.6.0-97.z2.sl6.x86_64

openafs-authlibs-1.6.0-93.pre4.sl6.x86_64

openafs-client-1.6.0-97.z2.sl6.x86_64

openafs-kpasswd-1.6.0-93.pre4.sl6.x86_64

openafs-compatible-1.6.0-93.pre4.sl6.x86_64

vzctl-lib-3.1-1.x86_64

vzctl-3.1-1.x86_64

Afs works perfectly on the host.

I can make the afs directory tree visible on the guests
by mount -n -t simfs /afs /vz/root/101/afs -o /afs

But I do not know how to get a token.

Klog results in:

open("/root/.AFSSERVER", O_RDONLY) = -1 ENOENT (No such file or directory)

open("/.AFSSERVER", O_RDONLY) = -1 ENOENT (No such file or directory)

open("/proc/fs/openafs/afs_ioctl", O_RDWR) = -1 ENOENT (No such file or directory)

open("/proc/fs/nnpfs/afs_ioctl", O_RDWR) = -1 ENOENT (No such file or directory)

afs_syscall(0x14, 0, 0x40185603, 0x7fffc4af1c70, 0) = -1 ENOSYS (Function not implemented)

write(2, "Unable to authenticate to AFS be...", 55Unable to authenticate to AFS because a pioctl
failed.

) = 55

exit_group(11682309) = ?

Any ideas are appreciated.

Subject: Re: Openafs in guests

Posted by [dzimi](#) on Sun, 29 Apr 2012 19:58:03 GMT

[View Forum Message](#) <> [Reply to Message](#)

yes you can. http://wiki.openvz.org/Bind_mounts
