
Subject: vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0

Posted by [farhatz](#) on Sun, 22 Jul 2012 18:49:27 GMT

[View Forum Message](#) <> [Reply to Message](#)

I have been trying to fix this problem for 2 days until now i have openvz installed. I create a VPS on command line i get stopped when trying to start the VPS container.

Quote:root@host [~]# vzctl start 111

Starting container ...

Container is mounted

Adding IP address(es): 67.222.131.209

RTNETLINK answers: File exists

vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0

Container start failed (try to check kernel messages, e.g. "dmesg | tail")

Stopping container ...

Container was stopped

Container is unmounted

root@host [~]#

Quote:root@host [~]# vzlist -a

CTID	NPROC	STATUS	IP_ADDR	HOSTNAME
------	-------	--------	---------	----------

111	-	stopped	67.222.131.209	-
-----	---	---------	----------------	---

121	-	stopped	-	-
-----	---	---------	---	---

root@host [~]#

help me please i dont understand with this conflict

and this is my configuration ip adres on my dedicated server

Quote:

root@host [~]# ifconfig

eth0 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8

inet addr:67.222.131.207 Bcast:67.222.131.255 Mask:255.255.255.0

inet6 addr: fe80::21d:9ff:fe98:20f8/64 Scope:Link

UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1

RX packets:5807 errors:0 dropped:0 overruns:0 frame:0

TX packets:3380 errors:0 dropped:0 overruns:0 carrier:0

collisions:0 txqueuelen:1000

RX bytes:785221 (766.8 KiB) TX bytes:497243 (485.5 KiB)

Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp1 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8

inet addr:67.222.131.208 Bcast:67.222.131.255 Mask:255.255.255.0

UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1

Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp2 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.209 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp3 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.210 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp4 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.211 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp5 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.212 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp6 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.213 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp7 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.214 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp8 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.215 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp9 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.216 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp10 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.217 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp11 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8

inet addr:67.222.131.218 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp12 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.219 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp13 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.220 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp14 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.221 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp15 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.222 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Memory:fdfc0000-fdfe0000

lo Link encap:Local Loopback
inet addr:127.0.0.1 Mask:255.0.0.0
inet6 addr: ::1/128 Scope:Host
UP LOOPBACK RUNNING MTU:16436 Metric:1
RX packets:341 errors:0 dropped:0 overruns:0 frame:0
TX packets:341 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:48863 (47.7 KiB) TX bytes:48863 (47.7 KiB)

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
RX packets:0 errors:0 dropped:0 overruns:0 frame:0
TX packets:0 errors:0 dropped:3 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:0 (0.0 b) TX bytes:0 (0.0 b)

root@host [~]#

what should I do next to fix this problem? please help me



Subject: Re: vps-net_add ERROR: Unable to add route ip route add
67.222.131.209 dev venet0

Posted by [curx](#) on Sun, 22 Jul 2012 19:29:19 GMT

[View Forum Message](#) <> [Reply to Message](#)

Remove the Container IPv4 from your hostnode, check your ifconfig post (eth0:cp2)

Bye,
Thorsten

Subject: Re: vps-net_add ERROR: Unable to add route ip route add
67.222.131.209 dev venet0

Posted by [farhatz](#) on Sun, 22 Jul 2012 22:32:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

and how to remove it by command ? please tell me sir i don't know anything of this problem
