
Subject: Venet on VLAN

Posted by [jdoo](#) on Wed, 13 Dec 2006 07:53:35 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
ifconfig eth0 0
vconfig add eth0 105
ifconfig eth0.105 192.168.1.1/24
```

```
vzctl set 2000 --ipadd 192.168.1.100 --save
```

ip add list.

```
nemo:scripts# diff -uN vps-functions.orig vps-functions
--- vps-functions.orig 2006-12-13 17:48:52.000000000 +1000
+++ vps-functions      2006-12-13 16:39:44.000000000 +1000
@@ -104,7 +104,7 @@
    /^[ \t]+inet / {
        if (dev != "") print (dev);
        dev="";
-    } | sed 's:$/'`
+    } | sed 's/[@:].*$/'`
    }
}
```

Subject: Re: Venet on VLAN

Posted by [Bobebe](#) on Fri, 15 Dec 2006 11:29:31 GMT

[View Forum Message](#) <> [Reply to Message](#)

HN1:/# vzlist

VEID	NPROC	STATUS	IP_ADDR	HOSTNAME
101	4	running	192.168.123.101	vz101
102	4	running	192.168.123.102	vz102

HN2: 10.1.71.53

???

HN1:/# ip r l

192.168.123.101 dev venet0 scope link
192.168.123.102 dev venet0 scope link
10.1.0.0/16 dev eth0 proto kernel scope link src 10.1.160.97
default via 10.1.0.1 dev eth0

HN1:/# ip a

2: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue
link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
inet 127.0.0.1/8 scope host lo
inet6 ::1/128 scope host
valid_lft forever preferred_lft forever
4: sit0: <NOARP> mtu 1480 qdisc noop
link/sit 0.0.0.0 brd 0.0.0.0
6: eth0: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc pfifo_fast qlen 1000
link/ether 00:02:b3:88:20:30 brd ff:ff:ff:ff:ff:ff
inet 10.1.160.97/16 brd 10.1.255.255 scope global eth0
inet6 fe80::202:b3ff:fe88:2030/64 scope link
valid_lft forever preferred_lft forever

HN1:/# vzctl exec 101 ip r l

191.255.255.1 dev venet0 scope link
default via 191.255.255.1 dev venet0

HN1:/# vzctl exec 101 ip a

1: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue

```
link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
inet 127.0.0.1/8 scope host lo
inet6 ::1/128 scope host
    valid_lft forever preferred_lft forever
3: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue
link/void
inet 127.0.0.1/32 scope host venet0
inet 192.168.123.101/32 scope global venet0:0
```

Subject: Re: Venet on VLAN
Posted by [Bobele](#) on Mon, 18 Dec 2006 13:52:22 GMT
[View Forum Message](#) <> [Reply to Message](#)

```
default via 10.1.0.1 dev eth0
```

```
route add -net 192.168.0.0 netmask 255.255.0.0 gw 10.1.160.97 dev eth0
```
