
Subject: reboot not start againts
Posted by [ardantus](#) on Mon, 15 Oct 2007 00:20:02 GMT
[View Forum Message](#) <> [Reply to Message](#)

i have hostnude with this spesification
ip4 3gb hd 80gb ram 1gb os HN fedora core 6
i have create 4 vps

```
[root@vps ~]# vzlist
  VEID   NPROC STATUS IP_ADDR   HOSTNAME
  140     4 running 192.168.0.140 slackware.vps.dj-avu.us
  141     4 running 192.168.0.141 slackware.vps.dj-avu.us
  142    21 running 192.168.0.142 fedora.vps.dj-avu.us
  144    12 running 192.168.0.144 fedora.vps.dj-avu.us
```

```
[root@vps ~]#
```

if i ssh to some vps example to 142 ip= 192.168.0.142 then type reboot -h now thats vps will rebooting but not run againts, thats problem also happens if i type

```
[root@vps ~]# vzctl exec 142 reboot
```

```
[root@vps ~]# vzlist
  VEID   NPROC STATUS IP_ADDR   HOSTNAME
  140     4 running 192.168.0.140 slackware.vps.dj-avu.us
  141     4 running 192.168.0.141 slackware.vps.dj-avu.us
  144    12 running 192.168.0.144 fedora.vps.dj-avu.us
```

```
[root@vps ~]#
```

if i type vzctl restart 142 / vzctl restart VEID its can run and thats vps will rebooting

```
[root@vps ~]# vzctl restart 142
Restarting VE
Starting VE ...
VE is unmounted
VE is mounted
Adding IP address(es): 192.168.0.142
Setting CPU units: 1000
Configure meminfo: 49152
Set hostname: fedora.vps.dj-avu.us
File resolv.conf was modified
VE start in progress...
```

```
[root@vps ~]#
[root@vps ~]# vzlist
  VEID   NPROC STATUS IP_ADDR   HOSTNAME
  140     4 running 192.168.0.140 slackware.vps.dj-avu.us
  141     4 running 192.168.0.141 slackware.vps.dj-avu.us
  142    21 running 192.168.0.142 fedora.vps.dj-avu.us
  144    12 running 192.168.0.144 fedora.vps.dj-avu.us
```

```
[root@vps ~]#
```

so what can i do to solved thats problem, i can everytime in my HN if some user reboot their vps

they will contact me for start their vps manually. on my HN i has set --onboot yes btw thats problem still hapen.

anybody can solved this problem and how to configure it so if some user reboot their vps can start againts no need i am to start manuali in HN.

Subject: Re: reboot not start againts

Posted by [curx](#) on Mon, 15 Oct 2007 04:58:54 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

every 5min, script /usr/share/vzctl/scripts/vpsreboot, should started via cron and started all reboot-marked VE's.

Please check if cron started this script and take a look in /var/log/vzctl.log if "vereboot" entries exist.

Subject: Re: reboot not start againts

Posted by [ardantus](#) on Thu, 18 Oct 2007 00:52:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

in my HN i have add crontab

```
5 * * * * /usr/share/vzctl/scripts/vpsreboot
```

btw some vps os can't reboot again

my HN os is fedora core and i have 2 vps slackware 11 and 2vps fedora core 7

both of fedora core can start againts but slackware die.

```
[root@vps ~]# vzlist
```

VEID	NPROC	STATUS	IP_ADDR	HOSTNAME
140	4	running	192.168.0.140	slackware.vps.dj-avu.us
141	4	running	192.168.0.141	slackware.vps.dj-avu.us
142	21	running	192.168.0.142	fedora.vps.dj-avu.us
144	12	running	192.168.0.144	fedora.vps.dj-avu.us

```
[root@vps ~]#
```

this is tail of logs

```
2007-10-18T05:35:01+0700 vereboot : VE 142 : reboot
```

```
2007-10-18T05:35:01+0700 vzctl : VE 142 : Starting VE ...
```

```
2007-10-18T05:35:01+0700 vzctl : VE 142 : VE is unmounted
```

```
2007-10-18T05:35:01+0700 vzctl : VE 142 : VE is mounted
```

2007-10-18T05:35:01+0700 venetclean : VE 142 : VE died, clear IPs: 192.168.0.142
2007-10-18T05:35:01+0700 vzctl : VE 142 : Adding IP address(es): 192.168.0.142
2007-10-18T05:35:04+0700 vzctl : VE 142 : Setting CPU units: 1000
2007-10-18T05:35:04+0700 vzctl : VE 142 : Configure meminfo: 49152
2007-10-18T05:35:04+0700 vzctl : VE 142 : Set hostname: fedora.vps.dj-avu.us
2007-10-18T05:35:04+0700 vzctl : VE 142 : File resolv.conf was modified
2007-10-18T05:35:04+0700 vzctl : VE 142 : VE start in progress...

2007-10-18T07:20:01+0700 venetclean : VE 141 : VE died, clear IPs: 192.168.0.141
2007-10-18T07:28:43+0700 vzctl : VE 141 : Starting VE ...
2007-10-18T07:28:43+0700 vzctl : VE 141 : VE is unmounted
2007-10-18T07:28:43+0700 vzctl : VE 141 : VE is mounted
2007-10-18T07:28:43+0700 vzctl : VE 141 : Adding IP address(es): 192.168.0.141
2007-10-18T07:28:45+0700 vzctl : VE 141 : Setting CPU units: 1000
2007-10-18T07:28:45+0700 vzctl : VE 141 : Configure meminfo: 49152
2007-10-18T07:28:45+0700 vzctl : VE 141 : Set hostname: slackware.vps.dj-avu.us
2007-10-18T07:28:45+0700 vzctl : VE 141 : File resolv.conf was modified
2007-10-18T07:28:45+0700 vzctl : VE 141 : VE start in progress...

141 is VEID of slackware when i type reboot thats vps die and need start manual with vzctl start
141