## Subject: Change IP address inside VE Posted by misch on Thu, 24 Apr 2008 07:07:25 GMT

View Forum Message <> Reply to Message

Hi,

due to the nature of a setup I have I have to change the IP address of my virtual server from inside the virtual server. Better: I want to add a cluster IP address to the interface.

Normally I have to do this with vzctl set 500 --ipaddr 1.2.3.4 from the host server. But:

Is this possible from within the virtual server to setup the ip address? What is the parameter vzctl set 500 --capability net\_admin:on good for? How can I use it?

Thanks for any hint.

--

Dr. Michael Schwartzkopff MultiNET Services GmbH

Addresse: Bretonischer Ring 7; 85630 Grasbrunn; Germany

Tel: +49 - 89 - 45 69 11 0 Fax: +49 - 89 - 45 69 11 21 mob: +49 - 174 - 343 28 75

mail: misch@multinet.de web: www.multinet.de

Sitz der Gesellschaft: 85630 Grasbrunn

---

PGP Fingerprint: F919 3919 FF12 ED5A 2801 DEA6 AA77 57A4 EDD8 979B

Skype: misch42

Subject: Re: Change IP address inside VE Posted by Christian Hofstaedtle on Thu, 24 Apr 2008 08:37:58 GMT View Forum Message <> Reply to Message

> due to the nature of a setup I have I have to change the IP address of my

<sup>\*</sup> Michael Schwartzkopff <misch@multinet.de> [080424 09:24]:

- > virtual server from inside the virtual server. Better: I want to add a
- > cluster IP address to the interface.
- > Is this possible from within the virtual server to setup the ip address? What
- > is the parameter
- > vzctl set 500 --capability net\_admin:on
- > good for? How can I use it?

## I think you've got two options:

- 1) You can use VETH devices instead of VENET. VETH is a more strict seperation of the network stuff, and full IP configuration is available in the VE.
- 2) \_If\_ you only want this VIP on \_ONE\_ host node, you probably can manually set up routing and ARP on the host node for your VIP, and then just use ifconfig inside the VEs. Haven't tried this out, but I'd assume it works.

## Christian