
Subject: how to uninstall openvz
Posted by [afreetbasha](#) on Thu, 03 Jul 2008 15:48:29 GMT
[View Forum Message](#) <> [Reply to Message](#)

how to uninstall openvz

Subject: Re: how to uninstall openvz
Posted by [maratrus](#) on Wed, 09 Jul 2008 16:09:59 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

uninstall vzctl, vzquota packages and ovzkernel.

Subject: Re: how to uninstall openvz
Posted by [afreetbasha](#) on Fri, 25 Jul 2008 13:33:24 GMT
[View Forum Message](#) <> [Reply to Message](#)

what steps or what way to uninstall vzctl, vzquota packages and ovzkernel plzzzzzzzz

Subject: Re: how to uninstall openvz
Posted by [kenjy](#) on Sat, 26 Jul 2008 16:32:23 GMT
[View Forum Message](#) <> [Reply to Message](#)

Just remove the packages for your distribution, for example in a debian base system just do:

```
root@windu:~# dpkg -l |grep vz
ii kernel-patch-openvz      028.18.1+etch6      server virtualization solution - kernel patc
ii linux-image-2.6.18+openvz custom01             Linux kernel binary image for version
2.6.18
ii vzctl                    3.0.11-13           server virtualization solution - control too
ii vzquota                  3.0.8-2             server virtualization solution - quota tools
root@windu:~#
```

Then just remove the openvz packages. Use the package manager of your own distribution (rpm, emerge, yum, apt ...)

Subject: Re: how to uninstall openvz
Posted by [dowdle](#) on Mon, 28 Jul 2008 05:54:06 GMT
[View Forum Message](#) <> [Reply to Message](#)

You really haven't given any information. I'm assume you want to remove OpenVZ from a host node? Or are you wanting to destroy an OpenVZ container?

If the former, it depends on what distro you are using on your host node and how you installed it in the first place. You'd usually just reverse the process. Say for a Fedora or CentOS/RHEL based host node you'd...

revert to your previous /etc/sysctl.conf
reboot to a non-openvz kernel
remove all of the openvz packages you installed

On other systems it may vary... but basically you reverse the install process.

Worst case scenario... you reformat the whole box... but that is only for the extremely lazy.

Subject: Re: how to uninstall openvz
Posted by [afreetbasha](#) on Mon, 28 Jul 2008 13:21:31 GMT
[View Forum Message](#) <> [Reply to Message](#)

i want to remove OpenVZ from a host node

Subject: Re: how to uninstall openvz
Posted by [dowdle](#) on Mon, 28 Jul 2008 16:31:46 GMT
[View Forum Message](#) <> [Reply to Message](#)

Given the replies that have been posted so far, I hope you have enough info to accomplish the task. If not, please feel free to ask additional, specific questions.
