
Subject: VE died ...

Posted by [Bobele](#) on Tue, 30 Sep 2008 17:44:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

vzlist -a -o veid,ip,name,numproc,status,hostname

1020004 10.100.102.53 arvdr

- mounted www.arvdr.de

vzctl.log:

2008-09-30T19:34:50+0200 vzctl : VE 1020004 : Starting VE ...

2008-09-30T19:34:50+0200 vzctl : VE 1020004 : VE is unmounted

2008-09-30T19:34:50+0200 vzctl : VE 1020004 : VE is mounted

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : Adding IP address(es): 10.100.102.53

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : Setting CPU units: 1000

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : Configure meminfo: 192000

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : Set hostname: www.arvdr.de

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : File resolv.conf was modified

2008-09-30T19:34:51+0200 vzctl : VE 1020004 : VE start in progress...

2008-09-30T19:35:01+0200 venetclean : VE 1020004 : VE died, clear IPs: 10.100.102.53

Subject: Re: VE died ...

Posted by [maratrus](#) on Wed, 01 Oct 2008 10:57:35 GMT

[View Forum Message](#) <> [Reply to Message](#)

Subject: Re: VE died ...

Posted by [Bobele](#) on Wed, 01 Oct 2008 13:37:25 GMT

[View Forum Message](#) <> [Reply to Message](#)

ovz-2:~# uname -a

Linux ovz-2.sv-system.com 2.6.18-openvz-12-1etch1-amd64 #1 SMP Fri May 4 23:37:24 MSD
2007 x86_64 GNU/Linux

```
ovz-2:~# vzctl --version
vzctl version 3.0.22-1dso1
```

```
ovz-2:/vz/template/cache# ls -l
-rw-r--r-- 1 root root 47263588 2008-05-13 10:50 ubuntu-8.04-amd64-minimal.tar.gz
```

vzctl.log.

<http://download.openvz.org/template/precreated/ubuntu-8.04-amd64-minimal.tar.gz>

```
ovz-2:/var/log# vzctl stop arvdr
Unable to stop: VE is not running
ovz-2:/var/log# vzctl start arvdr
Starting VE ...
Running: /usr/sbin/vzquota stat 1020004 -f
Running: /usr/sbin/vzquota off 1020004
VE is unmounted
Running: /usr/sbin/vzquota show 1020004
Running: /usr/sbin/vzquota on 1020004 -r 0 -b 4194404 -B 8388708 -i 200100 -l 220100 -e 0 -n 0
-s 0
Mounting root: /var/lib/vz/root/1020004 /var/lib/vz/private/1020004
VE is mounted
Set iptables mask 0x000017bf
Set features mask 0000000000000000/0000000000000000
Adding IP address(es): 10.100.102.53
Running: /usr/lib/vzctl/scripts/vps-net_add
Running VE script: /etc/vz/dists/scripts/debian-add_ip.sh
Setting CPU units: 1000
Configure meminfo: 192000
Set hostname: www.arvdr.de
Running VE script: /etc/vz/dists/scripts/debian-set_hostname.sh
Running VE script: /etc/vz/dists/scripts/set_dns.sh
File resolv.conf was modified
Running: /usr/sbin/vzquota stat 1020004 -f
Running: vzquota setlimit 1020004 -b 4194304 -B 8388608 -i 200000 -l 220000 -e 0 -n 0
VE start in progress...
ovz-2:/var/log#
```

```
2008-10-01T15:35:23+0200 vzctl : VE 1020004 : Unable to stop: VE is not running
2008-10-01T15:35:29+0200 vzctl : VE 1020004 : Starting VE ...
```

2008-10-01T15:35:29+0200 vzctl : VE 1020004 : Running: /usr/sbin/vzquota stat 1020004 -f
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Running: /usr/sbin/vzquota off 1020004
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : VE is unmounted
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Running: /usr/sbin/vzquota show 1020004
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Running: /usr/sbin/vzquota on 1020004 -r 0 -b 4194404 -B 8388708 -i 200100 -l 220100 -e 0 -n 0 -s 0
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Mounting root: /var/lib/vz/root/1020004
/var/lib/vz/private/1020004
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : VE is mounted
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Set iptables mask 0x000017bf
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Set features mask
0000000000000000/0000000000000000
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Adding IP address(es): 10.100.102.53
2008-10-01T15:35:30+0200 vzctl : VE 1020004 : Running: /usr/lib/vzctl/scripts/vps-net_add
2008-10-01T15:35:32+0200 vzctl : VE 1020004 : Running VE script:
/etc/vz/dists/scripts/debian-add_ip.sh
2008-10-01T15:35:34+0200 vzctl : VE 1020004 : Setting CPU units: 1000
2008-10-01T15:35:34+0200 vzctl : VE 1020004 : Configure meminfo: 192000
2008-10-01T15:35:34+0200 vzctl : VE 1020004 : Set hostname: www.arvdr.de
2008-10-01T15:35:34+0200 vzctl : VE 1020004 : Running VE script:
/etc/vz/dists/scripts/debian-set_hostname.sh
2008-10-01T15:35:34+0200 vzctl : VE 1020004 : Running VE script:
/etc/vz/dists/scripts/set_dns.sh
2008-10-01T15:35:35+0200 vzctl : VE 1020004 : File resolv.conf was modified
2008-10-01T15:35:35+0200 vzctl : VE 1020004 : Running: /usr/sbin/vzquota stat 1020004 -f
2008-10-01T15:35:35+0200 vzctl : VE 1020004 : Running: vzquota setlimit 1020004 -b 4194304
-B 8388608 -i 200000 -l 220000 -e 0 -n 0
2008-10-01T15:35:35+0200 vzctl : VE 1020004 : VE start in progress...

Subject: Re: VE died ...

Posted by [maratrus](#) on Wed, 01 Oct 2008 13:44:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

Subject: Re: VE died ...
Posted by [Bobele](#) on Wed, 01 Oct 2008 14:18:42 GMT
[View Forum Message](#) <> [Reply to Message](#)

2008-10-01T15:39:29+0200 vzctl : VE 1020004 : VE start in progress...
2008-10-01T15:40:02+0200 venetclean : VE 1020004 : VE died, clear IPs: 10.100.102.53

Subject: Re: VE died ...
Posted by [maratrus](#) on Wed, 01 Oct 2008 14:32:45 GMT
[View Forum Message](#) <> [Reply to Message](#)

http://forum.openvz.org/index.php?t=msg&goto=28942&# msg_28942

Subject: Re: VE died ...
Posted by [Bobele](#) on Wed, 01 Oct 2008 15:05:19 GMT
[View Forum Message](#) <> [Reply to Message](#)

```

ovz-2:/vz/private/1020004/etc/init.d# diff -u mountall.sh.ORIGINAL mountall.sh > mountall.sh.diff
ovz-2:/vz/private/1020004/etc/init.d# cat mountall.sh.diff
--- mountall.sh.ORIGINAL      2008-04-18 18:02:40.000000000 +0200
+++ mountall.sh 2008-10-01 16:53:24.000000000 +0200
@@ -76,7 +76,7 @@
     rm -f $INITCTL
     mknod -m 600 $INITCTL p
fi
- kill -USR1 1
+#--- kill -USR1 1

#
# Execute swapon command again, in case we want to swap to

```

>> Wait... Commenting `kill -USR1 1' makes VE starting but no services inside VE are started:

```

ovz-2:/# vzctl exec arvdr ps ax
PID TTY STAT TIME COMMAND
1 ? Ss 0:00 init
11572 ? Ss 0:00 /usr/sbin/apache2 -k start
11573 ? S 0:00 /usr/sbin/apache2 -k start
11574 ? Sl 0:00 /usr/sbin/apache2 -k start
11576 ? Sl 0:00 /usr/sbin/apache2 -k start
11772 ? Sl 0:04 /usr/bin/python /usr/bin/fail2ban-server -b -s /var/run/fail2ban/fail2ban.sock
11840 ? Ss 0:00 /usr/sbin/sshd
11851 ? Rs 0:00 ps ax

```

```

ovz-2:/# vzctl exec arvdr netstat -anp
Active Internet connections (servers and established)
Proto Recv-Q Send-Q Local Address           Foreign Address         State       PID/Program name
tcp        0      0 0.0.0.0:80              0.0.0.0:*               LISTEN      11572/apache2
tcp6       0      0 :::22                  :::*                   LISTEN      11840/sshd
Active UNIX domain sockets (servers and established)
Proto RefCnt Flags   Type       State      I-Node  PID/Program name  Path
unix    2      [ACC]  STREAM    LISTENING  8010797 11573/apache2     /var/run/apache2/cgisock.11572
unix    2      []     DGRAM          8008514 1/init           @/com/ubuntu/upstart
unix    2      [ACC]  STREAM    LISTENING  8011701 11772/python      /var/run/fail2ban/fail2ban.sock

```

```

ovz-2:/# vzctl exec arvdr ps ax
PID TTY STAT TIME COMMAND

```

```
1 ?      Ss   0:00 init
13899 ?   Rs   0:00 ps ax
```

```
ovz-2:/# vzctl exec arvdr netstat -anp
```

Active Internet connections (servers and established)

Proto	Recv-Q	Send-Q	Local Address	Foreign Address	State	PID/Program name
-------	--------	--------	---------------	-----------------	-------	------------------

Active UNIX domain sockets (servers and established)

Proto	RefCnt	Flags	Type	State	I-Node	PID/Program name	Path
-------	--------	-------	------	-------	--------	------------------	------

unix	2	[]	DGRAM		8012586	1/init	@/com/ubuntu/upstart
------	---	-----	-------	--	---------	--------	----------------------

Subject: Re: VE died ...

Posted by [Bobe](#) on Wed, 01 Oct 2008 15:08:17 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
ovz-2:/vz/private/1020004/etc/rc2.d# ls -l
```

```
insgesamt 4
```

```
-rw-r--r-- 1 root root 556 2008-04-19 07:05 README
```

```
lrwxrwxrwx 1 root root 18 2008-09-29 13:25 S10sysklogd -> ../init.d/sysklogd
```

```
lrwxrwxrwx 1 root root 13 2008-09-29 13:25 S16ssh -> ../init.d/ssh
```

```
lrwxrwxrwx 1 root root 18 2008-09-29 13:25 S21quotarpc -> ../init.d/quotarpc
```

```
lrwxrwxrwx 1 root root 17 2008-09-29 13:25 S91apache2 -> ../init.d/apache2
```

```
lrwxrwxrwx 1 root root 18 2008-09-29 13:25 S99fail2ban -> ../init.d/fail2ban
```

```
lrwxrwxrwx 1 root root 18 2008-09-29 13:25 S99rc.local -> ../init.d/rc.local
```

```
lrwxrwxrwx 1 root root 19 2008-09-29 13:25 S99rmnologin -> ../init.d/rmnologin
```

```
ovz-2:/vz/private/1020004/etc/rc2.d#
```

Subject: Re: VE died ...

Posted by [maratrus](#) on Wed, 01 Oct 2008 15:32:17 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote:

```
ovz-2:/vz/private/1020004/etc/rc2.d# ls -l
```

<http://download.openvz.org/debian/dists/etch/main/binary-amd64/base/>

Subject: Re: VE died ...

Posted by [Bobele](#) on Wed, 01 Oct 2008 15:54:21 GMT

[View Forum Message](#) <> [Reply to Message](#)

ovz-2:/# vzctl exec arvdr ps ef
VE is not running

<http://download.openvz.org/debian/dists/etch/main/binary-amd64/base/>

Subject: Re: VE died ...

Posted by [Bobele](#) on Wed, 01 Oct 2008 18:06:49 GMT

[View Forum Message](#) <> [Reply to Message](#)

fzkernel-2.6.18-amd64 ==> OpenVZ - Meta kernel 2.6.1812-fza-amd64 (028stab053.dso2) on amd64

http://download.openvz.org/debian/dists/etch/main/binary-amd64/base/linux-image-2.6.18-openvz-18-53.5d1-amd64_028.53.5d1__amd64.deb

http://download.openvz.org/debian-systs/pool/openvz/f/fzakernel-2.6.18-amd64/fzkernel-2.6.18-amd64_028stab053.dso2_amd64.deb