

---

Subject: VPS Start Script

Posted by [nick\\_chang](#) on Thu, 11 Dec 2008 03:59:38 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Dear All

I follow this document([http://wiki.openvz.org/Virtual\\_Ethernet\\_device](http://wiki.openvz.org/Virtual_Ethernet_device)) to change VPS network name.

But if I restart VPS. All setting recovery to old setting.

I don't know VPS start process.

How can tell me this process for VPS??

I want to write start and shutdown script to change this setting.

Thanks

BR

Nick

---

---

Subject: Re: VPS Start Script

Posted by [maratrus](#) on Thu, 11 Dec 2008 09:08:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

what in particular do you have in mind?

To save VEs parameters use --save option of vzctl utility.

---

---

Subject: Re: VPS Start Script

Posted by [nick\\_chang](#) on Thu, 11 Dec 2008 09:34:52 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello

Configure devices in CT0

```
[host-node]# ifconfig veth101.0 0
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/forwarding
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/veth101.0/proxy_arp
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/eth0/forwarding
[host-node]# echo 1 > /proc/sys/net/ipv4/conf/eth0/proxy_arp
```

How to save in CT0??

If VPS restart, all setting don't save in VPS and CT0

Nick

---

---

Subject: Re: VPS Start Script

Posted by [maratrus](#) on Thu, 11 Dec 2008 12:12:42 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

[http://wiki.openvz.org/w/index.php?title=Virtual\\_Ethernet\\_device&diff=5990&oldid=5989#Making\\_a\\_veth-device\\_persistent](http://wiki.openvz.org/w/index.php?title=Virtual_Ethernet_device&diff=5990&oldid=5989#Making_a_veth-device_persistent)

---