## Subject: How to remove VZ Posted by satimis on Sun, 19 Apr 2009 09:04:31 GMT

View Forum Message <> Reply to Message

Hi folks,

Host - Ubuntu 8.04 workstation Guest (VZ) - Ubuntu 8.04, base OS

I have 2 VZ running on this box. Both are base OS without X. They are working. Network connection established. They can be ping on their IP address.

root@vz0:/home/satimis# ls -al /var/lib/vzctl/veip/total 16 drwxr-xr-x 2 root root 4096 2009-04-18 21:40 . drwxr-xr-x 3 root root 4096 2008-09-24 18:54 .. -rw-r--r-- 1 root root 14 2009-04-19 14:47 101 -rw-r--r-- 1 root root 14 2009-04-19 14:47 102

Now I want to remove 102 completely. Whether run following command after stopping 102;

# rm /var/lib/vzctl/veip/102

?

Any further action is needed? Please advise. TIA

Edit:

I found it running;

\$ sudo vzctl destroy 102
Destroying VE private area: /var/lib/vz/private/102
VE private area was destroyed

\$ sudo vzctl start 102 VE config file does not exist

Any further action?

B.R. satimis

Subject: Re: How to remove VZ

Posted by maratrus on Tue, 21 Apr 2009 05:04:25 GMT

View Forum Message <> Reply to Message

# vzctl destroy 102

should be enough.

Please notice that 102.conf file is renamed to 102.conf.destroyed

Subject: Re: How to remove VZ

Posted by satimis on Tue, 21 Apr 2009 07:32:28 GMT

View Forum Message <> Reply to Message

maratrus wrote on Tue, 21 April 2009 13:04# vzctl destroy 102

should be enough.

Please notice that 102.conf file is renamed to 102.conf.destroyed Hi maratrus.

Thanks for your advice.

Shall I delete it?

B.R. satimis

Subject: Re: How to remove VZ

Posted by maratrus on Tue, 21 Apr 2009 07:36:11 GMT

View Forum Message <> Reply to Message

It's up to you.

If you don't need it, of course you may.

Subject: Re: How to remove VZ

Posted by satimis on Tue, 21 Apr 2009 07:56:37 GMT

View Forum Message <> Reply to Message

maratrus wrote on Tue, 21 April 2009 15:36lt's up to you.

If you don't need it, of course you may.

Noted and thanks

Page 3 of 3 ---- Generated from OpenVZ Forum