

---

Subject: OpenVZ kernel error

Posted by [KrunoN](#) on Sun, 24 May 2009 08:58:45 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hello, I'm having a problem with every VPS hosted on the node. HyperVM is working fine but I can't start/stop/restart any VPS on the node. I'm getting an error:

Alert: no\_kernel\_support\_for\_openvz\_check\_if\_right\_kernel

It worked fine all the time til yesterday, I have no idea what went wrong.

Anyway, here is my /etc/grub.conf file.

```
#boot=/dev/sda
default=6
timeout=5
splashimage=(hd0,0)/boot/grub/splash.xpm.gz
hiddenmenu
title CentOS (2.6.18-92.1.18.el5.028stab060.2PAE)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.18.el5.028stab060.2PAE ro root=/dev/sda 1
    initrd /boot/initrd-2.6.18-92.1.18.el5.028stab060.2PAE.img
title CentOS (2.6.18-92.1.22.el5)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.22.el5 ro root=/dev/sda1
    initrd /boot/initrd-2.6.18-92.1.22.el5.img
title CentOS (2.6.18-92.1.18.el5.028stab060.2)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.18.el5.028stab060.2 ro root=/dev/sda1
    initrd /boot/initrd-2.6.18-92.1.18.el5.028stab060.2.img
title CentOS (2.6.18-92.1.13.el5.028stab059.6PAE)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.13.el5.028stab059.6PAE ro root=/dev/sda 1
    initrd /boot/initrd-2.6.18-92.1.13.el5.028stab059.6PAE.img
title CentOS (2.6.18-92.1.18.el5)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.18.el5 ro root=/dev/sda1
    initrd /boot/initrd-2.6.18-92.1.18.el5.img
title CentOS (2.6.18-92.1.13.el5.028stab059.6)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-92.1.13.el5.028stab059.6 ro root=/dev/sda1
    initrd /boot/initrd-2.6.18-92.1.13.el5.028stab059.6.img
title CentOS (2.6.18-53.el5)
    root (hd0,0)
    kernel /boot/vmlinuz-2.6.18-53.el5 ro root=/dev/sda1
    initrd /boot/initrd-2.6.18-53.el5.img
```

After I changed default=1 and the whole node went down after a reboot. I hope I can get some help here about how to configure grub.conf to get the node together with all VPSs up and running

Thanks  
Best Regards

---

---

Subject: Re: OpenVZ kernel error  
Posted by [vijay\\_361](#) on Sun, 24 May 2009 13:05:34 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

default refers to which OS it should boot from grub.conf...

the default u set is 1 which is

```
title CentOS (2.6.18-92.1.22.el5)
root (hd0,0)
kernel /boot/vmlinuz-2.6.18-92.1.22.el5 ro root=/dev/sda1
initrd /boot/initrd-2.6.18-92.1.22.el5.img
```

This is not openvz supported kernel..

default 0 :refers to first title OS  
default 1 :refers to second title OS

.....

So set default to particular number.....

or - else simple thing is When it asks for grub loading ..  
press key to continue.....  
press any key  
Select the openvz kernel from the list and press enter or b....

for identifying openvz kernel it is having stab in the title  
like:title CentOS (2.6.18-92.1.18.el5.028stab060.2

I think u r asking this only..

---