

---

Subject: vzquota  
Posted by [deisler](#) on Mon, 19 Oct 2009 09:26:11 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Disk quota exceeded.

---

---

Subject: Re: vzquota  
Posted by [deisler](#) on Mon, 19 Oct 2009 11:46:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

[ 8814.121303] VZ QUOTA: disk softlimit exceeded for id=200  
[ 8814.121349] VZ QUOTA: disk quota softlimit expired for id=200

1.4 GB.

DISKSPACE="5000M:5000M"

---

---

Subject: Re: vzquota  
Posted by [deisler](#) on Mon, 19 Oct 2009 11:50:44 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

---

Subject: Re: vzquota  
Posted by [deisler](#) on Mon, 19 Oct 2009 11:55:45 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
/dev/sdc1 on /mnt/sde type ext3 (rw,noatime)
/mnt/sde/vz on /vz type none (rw,bind)
```

---

Subject: Re: vzquota  
Posted by [kir](#) on Mon, 19 Oct 2009 12:39:11 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
// Find out the default config file
# grep CONFIGFILE /etc/vz/vz.conf
CONFIGFILE=lalala
// In case you specify --config on 'vzctl create', check that one instead

// Find out the disk space limits in the default config
# grep DISK /etc/vz/conf/*lalala*

// Below we assume VEID=200

// Find out the disk space limits in VE config
# grep DISK /etc/vz/conf/200.conf

// Check current quota limits and usage
# cat /proc/vz/vzquota | sed -n '1p; /^200:/,+2p'

// Check real disk usage
# du -sh /vz/private/200
```

---

Subject: Re: vzquota  
Posted by [deisler](#) on Mon, 19 Oct 2009 13:16:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---