
Subject: bind mounts don't work?

Posted by [andreas2](#) on Thu, 03 Dec 2009 12:28:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hello!

I'm using Debian with kernel 2.6.26-2-openvz-686

mounting part of HW-node into container (/vz/private/NR/home/SPACE) doesn't show data inside the container. Outside it works (all data visible)

What can I do?

thanks,
Andrew

Subject: Re: bind mounts don't work?

Posted by [kir](#) on Thu, 03 Dec 2009 12:55:23 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote:What can I do?

Describe the situation in greater details. How you do the mount (what, to where), how you check etc.

Subject: Re: bind mounts don't work?

Posted by customer.joe@freemail.hu on Thu, 03 Dec 2009 15:00:52 GMT

[View Forum Message](#) <> [Reply to Message](#)

start VE then try mount to "/vz/root/NR/home/SPACE", instead of "/vz/private/NR/home/SPACE"

Subject: Re: bind mounts don't work?

Posted by [kir](#) on Thu, 03 Dec 2009 19:39:07 GMT

[View Forum Message](#) <> [Reply to Message](#)

Right,

- (1) you need to mount to /vz/root not /vz/private
 - (2) you need to do 'vzctl mount' before that
 - (3) you can automate it using vzctl mount scripts
-

Subject: Re: bind mounts work as documented

Posted by [andreas2](#) on Fri, 04 Dec 2009 07:58:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

Thanks, I mixed up root and private,
Seems, at later hours I'm unable to read...)
bye, Andrew

Subject: Re: bind mounts don't work?
Posted by [andreas2](#) on Thu, 10 Dec 2009 11:15:20 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi!
How can I dump(checkpoint) if external mounts there (mounted, because locked)?
vz:
ctl --ckpoint 120
dump 120
ctl destroy 120
dump --restore 120
ctl restore 120
restore 120 says: "Error: undump failed: No such file or dir
Error: mount point is missing: /home/SPACE. Stopping, Unmounting"

ctl mount (for allowing bind-mounts to root)
mount --bind/root/120/home/SPACE
leads to same error msg

thanks, Andrew
