

---

Subject: how to separate this server for 3 VPS's  
Posted by [ezak](#) on Tue, 22 Dec 2009 16:20:08 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

hi all,

I want some help for separate this server to 3 VPS

server: Intel(R) Core(TM)2 Quad CPU Q9650 @ 3.00GHz  
Ram 8 GB

VPS1 50% from server power

VPS2 25% from server power

VPS3 25 from server power

some choose don't know what to do on it, so I make it like this

VPS1

Disk Quota 50% from hard drive

Number Of Backups unlimited

Burstable Memory (MB)(openvz Only) 4GB

Guaranteed Memory (MB)(openvz Only) 4GB

Number Of Processes(openvz Only) unlimited

Cpu Usage (%) 100/CPU 200

Traffic (MB/month) 50% from bandwidth

Uplink Traffic(KB/s) unlimited

CPU UNITS (default 1000) unlimited

IO Priority (0-7) unlimited

Number Of CPUS unlimited

VPS2

Disk Quota 25% from hard drive

Number Of Backups unlimited

Burstable Memory (MB)(openvz Only) 2GB

Guaranteed Memory (MB)(openvz Only) 2GB

Number Of Processes(openvz Only) unlimited

Cpu Usage (%) 100/CPU 100

Traffic (MB/month) 25% from bandwidth

Uplink Traffic(KB/s) unlimited

CPU UNITS (default 1000) unlimited

IO Priority (0-7) unlimited

Number Of CPUS unlimited

VPS3

Disk Quota 25% from hard drive

Number Of Backups unlimited

Burstable Memory (MB)(openvz Only) 2GB

Guaranteed Memory (MB)(openvz Only) 2GB

Number Of Processes(openvz Only) unlimited

Cpu Usage (%) 100/CPU 100

Traffic (MB/month) 25% from bandwidth  
Uplink Traffic(KB/s) unlimited  
CPU UNITS (default 1000) unlimited  
IO Priority (0-7) unlimited  
Number Of CPUS unlimited

I don't know if I make it in right, so anyone can help me to know what should do, specially in the unlimited sections

and thanks for advice

---

---

Subject: Re: how to separate this server for 3 VPS's  
Posted by [kir](#) on Wed, 23 Dec 2009 09:29:41 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

You can use the result from vzsplrit 2 for the first server, and the result from vzsplrit 4 for the others. Then tweak the resulting configurations further.

---

---

Subject: Re: how to separate this server for 3 VPS's  
Posted by [ezak](#) on Wed, 23 Dec 2009 11:11:59 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

thanks, its much easy

but I did change in the first vps /etc/vz/conf/110.conf  
but doesn't changed on Limit on Hypervm ?  
should I need to restart, or I do something wrong ?

---