
Posted by [Zend](#) on Wed, 11 Aug 2010 08:09:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

Module	Size	Used by
vzethdev	9184	0
vznetdev	14564	2
simfs	4756	1
vzrst	116564	0
vzcpt	97860	0
tun	10148	2 vzrst,vzcpt
vzmon	23176	5 vzethdev,vznetdev,vzrst,vzcpt
xt_owner	3328	0
ipt_REDIRECT	2560	0
nf_nat_irc	2848	0
nf_nat_ftp	3296	0
iptable_nat	7268	1
nf_nat	16500	4 ipt_REDIRECT,nf_nat_irc,nf_nat_ftp,iptable_nat
xt_helper	2880	0
nf_conntrack_irc	5892	1 nf_nat_irc
nf_conntrack_ftp	7684	1 nf_nat_ftp
xt_length	2528	0
ipt_LOG	5924	0
ipt_ttl	2368	0
xt_tcpmss	2752	0
xt_TCPMSS	4448	0
ipt_REJECT	3552	0
xt_DSCP	3744	0
xt_dscp	3136	0
xt_multiport	3584	0
xt_limit	2948	0
iptable_mangle	4640	0
vzdquota	32796	1 [permanent]
ipv6	242240	33 vzrst,vzcpt,vzmon
vzdev	3624	4 vzethdev,vznetdev,vzmon,vzdquota
xt_tcpudp	3584	10
nf_conntrack_ipv4	17232	17 iptable_nat,nf_nat
xt_state	2784	9
xt_conntrack	4256	3
nf_conntrack	65480	10
nf_nat_irc,nf_nat_ftp,iptable_nat,nf_nat,xt_helper,nf_conntrack_irc,nf_conntrack_ftp,nf_conntrack_ipv4,xt_state,xt_conntrack		

```

iptables_filter      4288 2
ip_tables            11056 3 iptable_nat,iptable_mangle,iptable_filter
x_tables             14404 18
xt_owner,ipt_REJECT,iptable_nat,xt_helper,xt_length,ipt_LOG,ipt_ttl,xt_tcpmss,xt_TCPMSS,ip
t_REJECT,xt_DSCP,xt_dscp,xt_multiport,xt_limit,xt_tcpudp,xt_state,xt_contrack,ip_tables
ext2                 55336 1
loop                 13548 0
psmouse              33104 0
evdev                8736 0
serio_raw            5508 0
i2c_i801              8688 0
pcspkr               3200 0
video                17232 0
rng_core              4708 0
i2c_core             20596 1 i2c_i801
output               3680 1 video
button               6864 0
intel_agp            23428 0
agpgart              29576 1 intel_agp
ext3                 106120 1
jbd                  40276 1 ext3
mbcache              7876 2 ext2,ext3
sd_mod               22968 4
piix                  7336 0 [permanent]
ide_pci_generic      4676 0 [permanent]
ide_core             97000 2 piix,ide_pci_generic
ata_piix             15236 3
ata_generic          5444 0
libata               141376 2 ata_piix,ata_generic
scsi_mod             130444 2 sd_mod,libata
dock                 9072 1 libata
e100                 29900 0
mii                  5664 1 e100
thermal              15996 0
processor            33568 1 thermal
fan                  4964 0
thermal_sys          11624 4 video,thermal,processor,fan

```

```

IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS
ipt_tcpmss ipt_ttl ipt_length ip_contrack ip_tables"

```

FATAL: Could not load /lib/modules/2.6.26-2-opensvz-686/modules.dep: No such file or directory

Posted by [RXL_](#) on Wed, 11 Aug 2010 09:29:41 GMT

[View Forum Message](#) <> [Reply to Message](#)

Setting up a firewall that allows per-container configuration

Quote:If you want to use a firewall inside a container, please load these modules BEFORE starting the container:

Quote:If you want to use stateful firewall rules (and you should!) you will also need to make sure that 'ipt_state' is in the 'IPTABLES' option in your vz.conf file:
