
Subject: No pty and signal 9 VE autokill

Posted by [PASSCE](#) on Wed, 18 Aug 2010 17:29:51 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi everybody,

I'm running OpenVZ on 2.6.32.15 on my new server.

When I would like to start a fresh new VE, it says that it starts correctly

ex:

```
vzctl start 126
```

```
Starting container ...
```

```
Container is unmounted
```

```
Container is mounted
```

```
Setting CPU units: 1000
```

```
Container start in progress...
```

```
root@
```

but it died a few seconds later.

I already tried setting CONFIG_LEGACY_PTYS in the kernel, the result is the same.

When I tried to enter just after starting the VE, I got the message that it can't find any pty dev.

If I strace vzctl enter, I see that I got a sigkill.

If I remove udev, same problem, I can enter a few seconds in the VE and then got a Signal 9.

I'm running Gentoo inside VE and in Hypervisor.

Do you have any ideas of what I can do ?

PS : Nothing in dmesg (just CTXXX start and CTXXX stop)

EDIT : open a bug on bugzilla sorry

http://bugzilla.openvz.org/show_bug.cgi?id=1613

Subject: Re: No pty and signal 9 VE autokill

Posted by [maratrus](#) on Fri, 20 Aug 2010 10:58:53 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

most probably the reason is some sort of incompatibility between kernel and init-scripts inside the VE.

A couple of years ago there was a thread with similar problem (please, read the thread)

To find out the reason in your particular case I can recommend you to exclude all init-scripts by turns until you catch the bad one. It might be some call that an OpenVZ kernel processes incorrectly.

Subject: Re: No pty and signal 9 VE autokill
Posted by [PASSCE](#) on Fri, 20 Aug 2010 12:04:38 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,
Thanks for you answer, I found that
/sbin/reboot -f
was called during the boot process, but I don't know exactly which script is calling it .. (Maybe checkroot)

Is there any possibility to see the boot process of a VE ? (ie see the initscripts loading to know which one is launching reboot and maybe the error)?
Or anything to have a /dev/vcs1 in a VE ?

Thanks

Subject: Re: No pty and signal 9 VE autokill
Posted by [maratrus](#) on Fri, 20 Aug 2010 12:27:35 GMT
[View Forum Message](#) <> [Reply to Message](#)

Quote:
Is there any possibility to see the boot process of a VE

Unfortunately, there is no a native-OpenVZ solution
http://bugzilla.openvz.org/show_bug.cgi?id=477
http://bugzilla.openvz.org/show_bug.cgi?id=979

But there are some workarounds that can be read in
thread
