
Subject: Container_enter_failed
Posted by [danielmc](#) on Mon, 06 Sep 2010 21:49:05 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hello I found the solution of my problem here

http://wiki.openvz.org/Container_enter_failed

3) Debian : enter the VE manually.

but everyone know how can i automated this command on every host reboot and vm reboot?

I try whit a script in /etc/init.d/ but doesn't work!!

thx

Subject: Re: Container_enter_failed
Posted by [curx](#) on Tue, 07 Sep 2010 15:14:38 GMT
[View Forum Message](#) <> [Reply to Message](#)

is udev running in this container ?

Bye,
Thorsten

Subject: Re: Container_enter_failed
Posted by [danielmc](#) on Tue, 07 Sep 2010 17:51:37 GMT
[View Forum Message](#) <> [Reply to Message](#)

for information :

```
openvz:~# dpkg -l | grep vz
ii linux-image-2.6.26-2-openvz-686      2.6.26-25          Linux 2.6.26 image on
PPro/Celeron/PII/PIII/P4, OpenVZ support
ii linux-image-openvz-686             2.6.26+17+lenny1   Linux image on
PPro/Celeron/PII/PIII/P4, OpenVZ support
ii vzctl                               3.0.22-14          server virtualization solution - control tools
ii vzquota                             3.0.11-1           server virtualization solution - quota tools
openvz:~# cat /etc/issue
Debian GNU/Linux 5.0 \n \l
openvz:~# cat /vz/private/777/etc/issue
Ubuntu 10.04.1 LTS \n \l
```

I uninstall udev but now my network interfaces are not installed!!!!

I reinstall udev (in cache oufff) no think run why?

```
openvz:~# vzctl restart 777
```

```
Restarting VE
```

```
Stopping VE ...
```

```
VE was stopped
```

```
VE is unmounted
```

```
Starting VE ...
```

```
VE is mounted
```

```
Adding IP address(es): xxxxxxxxxx
```

```
Setting CPU units: 10000
```

```
Configure meminfo: 135168
```

```
Set hostname: xxxxxxxxxx
```

```
File resolv.conf was modified
```

```
VE start in progress...
```

```
openvz:~# vzctl enter 777
```

```
enter into VE 777 failed
```

```
Unable to open pty: No such file or directory
```

```
openvz:~# vzctl exec 777 "mount -t devpts devpts /dev/pts"
```

```
openvz:~# vzctl enter 777
```

```
entered into VE 777
```

```
root@mail:~#top
```

```
 1 root    20   0 2256 1180 992 S   0 0.2  0:00.08 init
28 root    20   0 2164  468 324 S   0 0.1  0:00.00 vzctl
29 root    20   0 2988 1660 1320 S  0 0.3  0:00.00 bash
40 root    20   0 2344 1084 888 R   0 0.2  0:00.02 top
```

why is nothing running!? I crash my preprod server F****

thx for your help...
