
Subject: Re: cant login to virtual machine from other computers

Posted by [alex905](#) on Sun, 03 Feb 2008 18:25:55 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
# Load additional iptables modules (nat helpers)
# Default: -none-
# Space separated list of nat helpers (e.g. 'ip_nat_ftp ip_nat_irc'), which
# are loaded after the firewall rules are applied. Options for the helpers are
# stored in /etc/modules.conf.
IPTABLES_MODULES=""

# Unload modules on restart and stop
# Value: yes|no, default: yes
# This option has to be 'yes' to get to a sane state for a firewall
# restart or stop. Only set to 'no' if there are problems unloading netfilter
# modules.
IPTABLES_MODULES_UNLOAD="yes"

# Save current firewall rules on stop.
# Value: yes|no, default: no
# Saves all firewall rules to /etc/sysconfig/iptables if firewall gets stopped
# (e.g. on system shutdown).
IPTABLES_SAVE_ON_STOP="no"

# Save current firewall rules on restart.
# Value: yes|no, default: no
# Saves all firewall rules to /etc/sysconfig/iptables if firewall gets
# restarted.
IPTABLES_SAVE_ON_RESTART="no"

# Save (and restore) rule and chain counter.
# Value: yes|no, default: no
# Save counters for rules and chains to /etc/sysconfig/iptables if
# 'service iptables save' is called or on stop or restart if SAVE_ON_STOP or
# SAVE_ON_RESTART is enabled.
IPTABLES_SAVE_COUNTER="no"

# Numeric status output
# Value: yes|no, default: yes
# Print IP addresses and port numbers in numeric format in the status output.
IPTABLES_STATUS_NUMERIC="yes"
```

i im pretty sure its not using nat. but if it is im guessing its going to be shown on the host machine's
(i take it that HN was a typo for HM)ifconfig. so here it is:

```
eth0    Link encap:Ethernet HWaddr 00:18:F8:0B:2F:52
```

inet addr:192.168.0.4 Bcast:192.168.0.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:85674 errors:0 dropped:0 overruns:0 frame:0
TX packets:141758 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:19927881 (19.0 MiB) TX bytes:25754199 (24.5 MiB)
Interrupt:20 Base address:0xcc00

eth0:1 Link encap:Ethernet HWaddr 00:18:F8:0B:2F:52
inet addr:192.168.0.5 Bcast:192.168.0.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
Interrupt:20 Base address:0xcc00

lo Link encap:Local Loopback
inet addr:127.0.0.1 Mask:255.0.0.0
UP LOOPBACK RUNNING MTU:16436 Metric:1
RX packets:199 errors:0 dropped:0 overruns:0 frame:0
TX packets:199 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:21462 (20.9 KiB) TX bytes:21462 (20.9 KiB)

venet0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
UP BROADCAST POINTOPOINT RUNNING NOARP MTU:1500 Metric:1
RX packets:94 errors:0 dropped:0 overruns:0 frame:0
TX packets:132 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:0
RX bytes:11127 (10.8 KiB) TX bytes:10582 (10.3 KiB)

as you can see i edited venet0 a bit if its wrong please say and i will revert it back.
