

---

Subject: Re: Using PPP in a Virtual Server  
Posted by [eroux](#) on Thu, 17 Aug 2006 14:30:39 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

```
[root@vs01-vc01 ~]# cat /proc/1/status
```

```
Name:  init
State:  S (sleeping)
SleepAVG:    88%
Tgid:  1
Pid:    1
PPid:   0
TracerPid:   0
FNid:  42
Uid:    0    0    0    0
Gid:    0    0    0    0
FDSize: 32
Groups: 0 1 2 3 4 6 10
envID:  42
VPid:   1
PNState:    0
StopState:  0
VmPeak:    2008 kB
VmSize:    1996 kB
VmLck:      0 kB
VmHWM:     672 kB
VmRSS:     672 kB
VmData:    196 kB
VmStk:     88 kB
VmExe:     32 kB
VmLib:    1632 kB
VmPTE:     40 kB
StaBrk: 08051000 kB
Brk:  088a2000 kB
StaStk: bffcdeb0 kB
ExecLim:    08050000
Threads:    1
SigQ:  0/8052
SigPnd: 0000000000000000
ShdPnd: 0000000000000000
SigBlk: 0000000000000000
SigIgn: ffffffff57f0d8fc
SigCgt: 00000000280b2603
SigSvd: 0000000000000000
CapInh: 000000005ffffeff
CapPrm: 000000005ffffeff
CapEff: 000000005ffffeff
Cpus_allowed: ffffffff
Mems_allowed: 1
```

TaskUB: 42  
MMUB: 42  
[root@vs01-vc01 ~]#

No go even with:

```
/etc/vz/conf/42.confCAPABILITY="CHOWN:on DAC_OVERRIDE:on DAC_READ_SEARCH:on  
FOWNER:on FSETID:on KILL:on SETGID:on SETUID:on LINUX_IMMUTABLE:on  
NET_BIND_SERVICE:on NET_BROADCAST:on NET_ADMIN:on NET_RAW:on IPC_LOCK:on  
IPC_OWNER:on SYS_MODULE:on SYS_RAWIO:on SYS_CHROOT:on SYS_PTRACE:on  
SYS_PACCT:on SYS_ADMIN:on SYS_BOOT:on SYS_NICE:on SYS_RESOURCE:on  
SYS_TIME:on SYS_TTY_CONFIG:on MKNOD:on LEASE:on"
```

So I don't know...

---