

---

Subject: Re: Checkpoint bug

Posted by [dagr](#) on Thu, 07 Dec 2006 11:25:36 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Tried also vzctl 3.0.13 - and 2.6.18-ovz028test005.1-smp

restore on same HN

```
[dagr@ssw2-ca utils]$ sudo vzctl restore 10121 --undump --dumpfile ./img
```

```
Restoring VE ...
```

```
Starting VE ...
```

```
VE is unmounted
```

```
VE is mounted
```

```
undump...
```

```
Adding IP address(es): 10.1.2.1
```

```
Setting CPU units: 1000
```

```
//////////
```

Then its just hangs and server hangs as well , (on kernel 2.6.9 it hanged only during reboot) , so again hard reset. On console see this

```
[<c02889cf>] unblank_screen+0xf/0x20
```

```
[<c023cb16>] bust_spinlocks+0x36/0x50
```

```
[<c010f43a>] smp_nmi_callback+0x6a/0x90
```

```
[<c010546c>] do_nmi+0x7c/0xa0
```

```
[<c0103d12>] nmi_stack_correct+0x1d/0x22
```

```
[<c011007b>] do_boot_cpu+0x16b/0x2e0
```

```
[<c0494c8d>] __read_lock_failed+0x5/0x18
```

```
[<c0496e9b>] _read_lock+0xb/0x10
```

```
[<c0132f7d>] send_group_sig_info+0xd/0x40
```

```
[<c012f894>] lock_timer_base+0x24/0x50
```

```
[<c0129d0e>] it_real_fn+0x2e/0x80
```

```
[<c0129ce0>] it_real_fn+0x0/0x80
```

```
[<c0140d1a>] hrtimer_run_queues+0x8a/0x110
```

```
[<c0130cd7>] run_timer_softirq+0x27/0x1e0
```

```
[<c012b322>] __do_softirq+0xa2/0x150
```

```
[<c0105ce5>] do_softirq+0x55/0xb0
```

```
=====
```

```
[<c0130b8a>] update_process_times+0x4a/0xc0
```

```
[<c011122e>] smp_apic_timer_interrupt+0x8e/0xb0
```

```
[<c0100e6c>] default_idle+0x2c/0x60
```

```
[<c0103bbb>] apic_timer_interrupt+0x1f/0x24
```

```
[<c0100e6c>] default_idle+0x2c/0x60
```

```
[<c0100f32>] cpu_idle+0x72/0x90
```