Subject: vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0
Posted by farhatz on Sun, 22 Jul 2012 18:49:27 GMT
View Forum Message <> Reply to Message

I have been trying to fix this problem for 2 days until now i have openvz installed. I create a VPS on command line i get stopped when trying to start the VPS container.

Quote:root@host [~]# vzctl start 111
Starting container ...
Container is mounted
Adding IP address(es): 67.222.131.209
RTNETLINK answers: File exists
vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0
Container start failed (try to check kernel messages, e.g. "dmesg | tail")
Stopping container ...
Container was stopped
Container is unmounted
root@host [~]#

Quote:root@host [~]# vzlist -a
CTID NPROC STATUS IP_ADDR HOSTNAME
111 - stopped 67.222.131.209 -
121 - stopped - -
root@host [~]#

help me please i dont understand with this conflict
and this is my configuration ip addres on my dedicated server

Quote:
root@host [~]# ifconfig
eth0 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.207 Bcast:67.222.131.255 Mask:255.255.255.0
inet6 addr: fe80::21d:9ff:fe98:20f8/64 Scope:Link
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
RX packets:5807 errors:0 dropped:0 overruns:0 frame:0
TX packets:3380 errors:0 dropped:0 overruns:0 carrier:0
collisions:0 txqueuelen:1000
RX bytes:785221 (766.8 KiB) TX bytes:497243 (485.5 KiB)
Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp1 Link encap:Ethernet HWaddr 00:1D:09:98:20:F8
inet addr:67.222.131.208 Bcast:67.222.131.255 Mask:255.255.255.0
UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1

```
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp2  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.209  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp3  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.210  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp4  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.211  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp5  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.212  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp6  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.213  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp7  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.214  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp8  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.215  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp9  Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.216  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp10 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.217  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp11 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
```

```
        inet addr:67.222.131.218  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp12 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.219  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp13 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.220  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp14 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.221  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

eth0:cp15 Link encap:Ethernet  HWaddr 00:1D:09:98:20:F8
        inet addr:67.222.131.222  Bcast:67.222.131.255  Mask:255.255.255.0
        UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
        Interrupt:20 Memory:fdfc0000-fdfe0000

lo        Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:341 errors:0 dropped:0 overruns:0 frame:0
        TX packets:341 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:48863 (47.7 KiB)  TX bytes:48863 (47.7 KiB)

venet0    Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:3 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

root@host [~]#
```

what should I do next to fix this problem? please help me

Subject: Re: vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0
Posted by curx on Sun, 22 Jul 2012 19:29:19 GMT
View Forum Message <> Reply to Message

Remove the Container IPv4 from your hostnode, check your ifconfig post (eth0:cp2)

Bye,
Thorsten

Subject: Re: vps-net_add ERROR: Unable to add route ip route add 67.222.131.209 dev venet0
Posted by farhatz on Sun, 22 Jul 2012 22:32:55 GMT
View Forum Message <> Reply to Message

and how to remove it by command ? please tell me sir i don't know anything of this problem