Subject: adding secondary IP
Posted by Markus Hardiyanto on Mon, 23 Apr 2007 07:02:28 GMT
View Forum Message <> Reply to Message

how can i add secondary IP for a VE? i need to add this for nameserver IP.

do i need to run
vzctl set VEID --ipadd

for the second IP?
Best Regards,
Markus

Send instant messages to your online friends http://uk.messenger.yahoo.com

Subject: Re: adding secondary IP
Posted by Rudy Setiawan on Mon, 23 Apr 2007 07:16:25 GMT
View Forum Message <> Reply to Message

Hallo Markus,

Yep2 just use vzctl set <VEID> --ipadd <ip> --save

the --save flag will save the IP information in the VEID.conf for that
particular VEID.

Regards,
Rudy

Markus Hardiyanto wrote:
> how can i add secondary IP for a VE? i need to add this for nameserver IP.
>
> do i need to run
> vzctl set VEID --ipadd
>
> for the second IP?
> Best Regards,
> Markus
>
>
>
> Send instant messages to your online friends http://uk.messenger.yahoo.com

Subject: Re: adding secondary IP
Posted by Vasily Tarasov on Mon, 23 Apr 2007 08:38:59 GMT
View Forum Message <> Reply to Message

Hello Markus,

If you wish to have a second IP address for a VE you should give
HN@root# vzctl set <veid> --ipadd <second_ip> --save
command. It will create second venet interface with specified IP address
in VE.

But if you wish to set a nameserver for VE, then use
HN@root# vzctl set <veid> --nameserve <nameserver_ip> --save
command. It will modify /etc/resolv.conf file in VE and produce other
distribution-specific actions in order your VE to be able to resolve
domain names.

HTH,
Vasily.

Markus Hardiyanto wrote:
> how can i add secondary IP for a VE? i need to add this for nameserver IP.
>
> do i need to run
> vzctl set VEID --ipadd
>
> for the second IP?
> Best Regards,
> Markus
>
>
>
> Send instant messages to your online friends http://uk.messenger.yahoo.com