

---

Subject: Can't umount: /vz/root/veid: Invalid argument  
Posted by [its\\_joe](#) on Mon, 02 Aug 2010 01:01:27 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

When trying to start vps using below command.

```
vzctl start veid
```

gets below error

```
-----  
Starting container ...  
Can't umount: /vz/root/veid: Invalid argument  
Adding IP address(es): ip  
Setting CPU limit: 200  
Setting CPU units: 1000  
Configure meminfo: 131072  
Set hostname: hostname  
Error: Unable to apply new quota values quota not running  
Container start failed  
Stopping container ...  
Container was stopped  
Error: Unable to apply new quota values quota not running  
Can't umount: /vz/root/veid: Invalid argument  
-----
```

Please let us know if any solution asap.

Thank you.

---

---

Subject: Re: Can't umount: /vz/root/veid: Invalid argument  
Posted by [omega](#) on Tue, 18 Jan 2011 18:39:12 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi!  
I'm just having the same problem and do not find anything in the logs. Were you able to solve it?  
It was very nice if you could give a hint.  
Thanks in advance  
Oliver

---

---

Subject: Re: Can't umount: /vz/root/veid: Invalid argument  
Posted by [Kristian0911](#) on Fri, 06 May 2011 00:14:48 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hello,

Try to umount /vz/root/VEID and then start the container.

It should solve the issue.

Thanks.

---

Subject: Re: Can't umount: /vz/root/veid: Invalid argument  
Posted by [chintootom](#) on Thu, 21 Jun 2012 04:58:16 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

First you have to check the process that running on that vps.

```
ps aux |grep veid
```

Then kill all that process running on the /vz/root/veid

Then umount the folder and start the vps.

```
vzctl start veid.
```