Posted by azagzin on Tue, 13 May 2008 12:36:50 GMT
View Forum Message <> Reply to Message

http://download.openvz.org/template/precreated/contrib/cento s-5-i386-minimal.tar.gz

azagzin ~ # vzctl start 101
Starting VE ...
Running: /usr/sbin/vzquota show 101
Running: /usr/sbin/vzquota on 101 -r 0 -b 1048676 -B 1153124 -i 200100 -I 220100 -e 0 -n 0 -s 0
Mounting root: /vz/root/101 /vz/private/101
VE is mounted
Unable to set capability: Invalid argument
Unable to set capability
VE start failed
Running: /usr/sbin/vzquota stat 101 -f
Running: vzquota setlimit 101 -b 1048576 -B 1153024 -i 200000 -I 220000 -e 0 -n 0
Running: /usr/sbin/vzquota stat 101 -f
Running: /usr/sbin/vzquota off 101
VE is unmounted

azagzin ~ # uname -a
Linux azagzin 2.6.24-ovz004 #6 SMP Mon May 12 17:16:54 EEST 2008 i686 Intel(R) Core(TM)2 CPU 6300 @ 1.86GHz GenuineIntel GNU/Linux

azagzin ~ # cat /proc/self/status
Name: cat
State: R (running)
Tgid: 20108
Pid: 20108
PPid: 18606
TracerPid: 0
Uid: 0   0   0   0
Gid: 0   0   0   0

FDSize: 256
Groups: 0 1 2 3 4 6 10 11 20 26 27 1006
envID: 0
VPid: 20108
PNState: 0
StopState: 0
VmPeak: 3660 kB
VmSize: 3660 kB
VmLck: 0 kB
VmHWM: 464 kB
VmRSS: 464 kB
VmData: 156 kB
VmStk: 84 kB
VmExe: 28 kB
VmLib: 1316 kB
VmPTE: 16 kB
Threads: 1
SigQ: 0/32607
SigPnd: 0000000000000000
ShdPnd: 0000000000000000
SigBlk: 0000000000000000
SigIgn: 0000000000000000
SigCgt: 0000000000000000
SigSvd: 0000000000000200
CapInh: 0000000000000000
CapPrm: 00000000fffffeff
CapEff: 00000000fffffeff
Cpus_allowed: 00000003
Mems_allowed: 1
voluntary_ctxt_switches: 1
nonvoluntary_ctxt_switches: 0
TaskUB: 0
MMUB: 0

azagzin ~ #cat /etc/vz/conf/101.conf

ONBOOT="no"

# UBC parameters (in form of barrier:limit)
KMEMSIZE="11055923:11377049"
LOCKEDPAGES="256:256"
PRIVVMPAGES="65536:69632"
SHMPAGES="21504:21504"
NUMPROC="240:240"
PHYSPAGES="0:2147483647"
VMGUARPAGES="33792:2147483647"

```
OOMGUARPAGES="26112:2147483647"
NUMTCPSOCK="360:360"
NUMFLOCK="188:206"
NUMPTY="16:16"
NUMSIGINFO="256:256"
TCPSNDBUF="1720320:2703360"
TCPRCVBUF="1720320:2703360"
OTHERSOCKBUF="1126080:2097152"
DGRAMRCVBUF="262144:262144"
NUMOTHERSOCK="360:360"
DCACHESIZE="3409920:3624960"
NUMFILE="9312:9312"
AVNUMPROC="180:180"
NUMIPTENT="128:128"

# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="1048576:1153024"
DISKINODES="200000:220000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"


VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="centos-5-i386-minimal"
ORIGIN_SAMPLE="vps.basic"
HOSTNAME="centos-vz"
IP_ADDRESS="x.x.x.x"
NAMESERVER="x.x.x.x"
```

```
sys-cluster/vzctl-3.0.22
sys-fs/vzquota-3.0.11
```

File Attachments

1) 2.6.24-ovz004.1.config, downloaded 629 times