Subject: modprobe fuse problem
Posted by Haider on Tue, 09 Sep 2008 01:33:51 GMT
View Forum Message <> Reply to Message

i compile & install fuse and sshfs without any problem but when i try to modprobe fuse i get
FATAL: Error inserting fuse
(/lib/modules/2.6.18-92.1.1.el5.028stab057.2/kernel/fs/fuse/ fuse.ko):Operation not permitted
and when i try to connect thourgh sshfs myserver:/ /mnt/test/ i get /dev/fuse: permission denied
any solution for these problems?

Subject: Re: modprobe fuse problem
Posted by khorenko on Tue, 09 Sep 2008 06:31:35 GMT
View Forum Message <> Reply to Message

all modules should be loaded on a Hardware Node (before the Container start in general), you cannot load any modules from inside a Container or that would be a security hole.

--
Konstantin

Subject: Re: modprobe fuse problem
Posted by Haider on Tue, 09 Sep 2008 14:12:23 GMT
View Forum Message <> Reply to Message

can u tell me how can i load it on hardware node?? cuz i really really need that module to run

Subject: Re: modprobe fuse problem
Posted by khorenko on Wed, 10 Sep 2008 09:49:48 GMT
View Forum Message <> Reply to Message

modprobe fuse

Subject: Re: modprobe fuse problem
Posted by Haider on Wed, 10 Sep 2008 13:29:09 GMT
View Forum Message <> Reply to Message

the problem is when i run modprobe fuse
i get

"FATAL: Error inserting fuse
(/lib/modules/2.6.18-92.1.1.el5.028stab057.2/kernel/fs/fuse/ fuse.ko):Operation not permitted"

and

when i try to connect thourgh
sshfs myserver:/ /mnt/test/
i get "/dev/fuse: permission denied"

any solution for these problems?

Subject: Re: modprobe fuse problem
Posted by khorenko on Wed, 10 Sep 2008 13:38:43 GMT
View Forum Message <> Reply to Message

modprobe fuse

execute this command on a Hardware Node, not inside a Container.
http://wiki.openvz.org/Hardware_node
