
Subject: Re: Server4you Server and Connecting to the Internet and from the Internet

Posted by [dragon001](#) on Mon, 26 Feb 2007 18:01:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

by the way, more about the ve

```
root@localhost:/# ifconfig -a
```

```
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)
```

```
venet0  Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:24 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:1398 (1.3 KiB)
```

```
venet0:0 Link encap:UNSPEC HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        inet addr:11.22.33.172  P-t-P:11.22.33.172  Bcast:0.0.0.0  Mask:255.255.255.255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
```

the /etc/network/interfaces

```
# This configuration file is auto-generated.
# WARNING: Do not edit this file, otherwise your changes will be lost.
# Please edit template /etc/network/interfaces.template instead.
```

```
# Auto generated venet0 interfaces
```

```
auto venet0 lo
iface venet0 inet static
    address 127.0.0.1
    netmask 255.255.255.255
    broadcast 0.0.0.0
    up route add -net 192.0.2.1 netmask 255.255.255.255 dev venet0
    up route add default gw 192.0.2.1
iface lo inet loopback
```

```
auto venet0:0
iface venet0:0 inet static
```

```
address 11.22.33.172
netmask 255.255.255.255
broadcast 0.0.0.0
```

I tried to add routing information or korrekt the netmask, but every time i restarted the ve, every setting is reseted to this.

I tried this as Routes

```
up route add -net 11.22.33.1 netmask 255.255.255.0 venet0
up route add default gw 11.22.33.1 venet0
```

But as i said, vzctl overwrites my settings.