

---

Subject: AW: Vzctl set --userpasswd question  
Posted by [Dietmar Maurer](#) on Mon, 25 Jun 2007 11:28:36 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

OK, now the VPS stpos correctly, but i get the following error:

```
vzctl set 777 --userpasswd root:test
Starting VE ...
VE is mounted
VE start in progress...
Stopping VE ...
VE was stopped
VE is unmounted
Configure meminfo: 309371
Unable to set meminfo: Invalid argument
```

- Dietmar

```
> -----Ursprüngliche Nachricht-----
> Von: Kir Kolyskin [mailto:kir@openvz.org]
> Gesendet: Samstag, 23. Juni 2007 00:37
> An: Dietmar Maurer
> Cc: devel@openvz.org
> Betreff: Re: [Devel] Vzctl set --userpasswd question
>
> I'm not really sure, but I guess this is old vzctl vs. new
> kernel incompatibility, solved by
> http://git.openvz.org/?p=vzctl;a=commitdiff;h=4766d1f711a73e79
29530a5a3f50d749e0f9de6a
>
> Can you please try vzctl-3.0.16 with this patch, or latest
> vzctl from git, and report your results here?
>
> Regards,
> Kir.
>
> Dietmar Maurer wrote:
>> Hi all,
>>
>> I am trying to set a password with the --userpasswd option,
> the VPS is
>> not
>> running:
>>
>>
>>> vzctl set 777 --userpasswd root:test
>>>
>> Starting VE ...
```

```

> > VE is mounted
> > VE start in progress...
> > Stopping VE ...
> > Unable to stop VE: operation timed out Configure meminfo: 309371
> >
> > Looks like vzctl start init (runlevel 2) on that VPS, so we
> get a timeout.
> > Output form ps for that VPS:
> >
> >
> >> ps auxww
> >>
> > USER    PID %CPU %MEM  VSZ  RSS TTY    STAT START
> TIME COMMAND
> > root      1 0.3 0.0  1948  640 ?     Ss  11:17
> 0:00 init [2]
> > root    18348 0.0 0.0  2760 1436 ?     Ss  11:17
> 0:00 /bin/sh
> > /etc/init.d/rc 2
> > root    18357 0.0 0.0  1632  612 ?     Ss  11:17  0:00
> > /sbin/syslogd
> > ...
> >
> > So why does it start init - is that expected behavior, or
> is something
> > wrong with my custom template?
> >
> > The vzctl man page say:
> >
> >
> >> --userpasswd user:password
> >> ...
> >> In case VE root is not mounted, it is automatically
> >> mounted,
> >>
> >> then
> >
> >> all appropriate file changes are applied, then
> it is unmounted.
> >>
> >
> > vzctl version 3.0.16-5dso1
> > Linux vz-etch 2.6.18-028stab035.1-ovz-smp #1 SMP Wed Jun 13
> 22:08:06
> > CEST
> > 2007 i686 GNU/Linux
> > OS Debian etch
> >

```

> > - Dietmar

> >

> >

> --

> This e-mail is checked by Proxmox - Virus and Spam Mail

> Gateway <http://www.proxmox.com>

>

>

---