
Subject: Re: Multicast between VEs

Posted by [ataraxis](#) on Tue, 03 Jul 2007 13:47:22 GMT

[View Forum Message](#) <> [Reply to Message](#)

Quote: (ip a ls, ip ro ls in VE and HN).

HN

ip a ls

```
2: eth0: <BROADCAST,MULTICAST,UP,10000> mtu 1500 qdisc pfifo_fast qlen 1000
   link/ether 00:14:22:fe:7d:d8 brd ff:ff:ff:ff:ff:ff
   inet XXX.YYY.ZZZ.253/27 brd XXX.YYY.ZZZ.255 scope global eth0
4: eth1: <BROADCAST,MULTICAST> mtu 1500 qdisc noop qlen 1000
   link/ether 00:14:22:fe:7d:d9 brd ff:ff:ff:ff:ff:ff
6: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue
   link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
   inet 127.0.0.1/8 scope host lo
1: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue
   link/void
```

ip ro ls

```
224.0.66.66 dev eth0 scope link
XXX.YYY.ZZZ.248 dev venet0 scope link
XXX.YYY.ZZZ.217 dev venet0 scope link
XXX.YYY.ZZZ.216 dev venet0 scope link
XXX.YYY.ZZZ.213 dev venet0 scope link
XXX.YYY.ZZZ.245 dev venet0 scope link
XXX.YYY.ZZZ.212 dev venet0 scope link
XXX.YYY.ZZZ.246 dev venet0 scope link
XXX.YYY.ZZZ.215 dev venet0 scope link
XXX.YYY.ZZZ.247 dev venet0 scope link
XXX.YYY.ZZZ.214 dev venet0 scope link
XXX.YYY.ZZZ.211 dev venet0 scope link
XXX.YYY.ZZZ.243 dev venet0 scope link
XXX.YYY.ZZZ.210 dev venet0 scope link
XXX.YYY.ZZZ.224/27 dev eth0 proto kernel scope link src XXX.YYY.ZZZ.253
224.0.0.0/4 dev eth0 scope link
default via XXX.YYY.ZZZ.225 dev eth0
```

VE

ip a ls

```
1: lo: <LOOPBACK,UP,10000> mtu 16436 qdisc noqueue
   link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
```

```
inet 127.0.0.1/8 scope host lo
3: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,10000> mtu 1500 qdisc noqueue
    link/void
    inet 127.0.0.1/32 scope host venet0
    inet XXX.YYY.ZZZ.210/32 scope global venet0:0
```

```
ip ro ls
```

```
192.0.2.1 dev venet0  scope link
default via 192.0.2.1 dev venet0
```

Quote:Do you use venet or veth device in VE?
venet
