

---

Subject: Re: Disk quota exceeded

Posted by [jpastore](#) on Tue, 03 Jul 2007 15:46:37 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

thanks for the pointer to the conf file I can look at!

my point is that I do not want quotas of any kind. I'm trying to figure out why when I scp from my old server to the VE on this new box am I get an error of: Disk quota exceeded

when I never configured traditional quotas. I didn't configure per ve quotas either.

how do I confirm the what the ve quota is set to? and as a follow up either disable it or really increase it.

contents of the conf file:

VERSION="2"

ONBOOT="yes"

# UBC parameters (in form of barrier:limit)

# Primary parameters

AVNUMPROC="40:40"

NUMPROC="400:400"

NUMTCPSOCK="500:500"

NUMOTHERSOCK="500:500"

VMGUARPAGES="102400:102400"

# Secondary parameters

KMEMSIZE="16384000:18022400"

TCPSNDBUF="5365760:10485760"

TCPRCVBUF="5365760:10485760"

OTHERSOCKBUF="1503232:4063232"

DGRAMRCVBUF="262144:262144"

OOMGUARPAGES="102400:102400"

# Auxiliary parameters

LOCKEDPAGES="4096:4096"

SHMPAGES="131072:131072"

PRIVVMPAGES="262144:292912"

NUMFILE="8192:8192"

NUMFLOCK="200:220"

NUMPTY="64:64"

NUMSIGINFO="512:512"

DCACHESIZE="4194304:4317184"

PHYSPPAGES="0:9223372036854775807"

NUMIPTENT="128:128"

```
# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="10000000000:15000000000"
DISKINODES="200000:220000"
QUOTATIME="0"
```

```
# CPU fair sheduler parameter
CPUUNITS="1000"
OFFLINE_MANAGEMENT="yes"
VE_ROOT="/vz/root/$VEID"
VE_PRIVATE="/vz/private/$VEID"
OSTEMPLATE="centos-4-x86_64-minimal"
ORIGIN_SAMPLE="vps.basic"
IP_ADDRESS="192.168.0.51"
```

---