
Subject: Re: iptables

Posted by [eugenio pacheco](#) on Thu, 30 Mar 2006 17:22:42 GMT

[View Forum Message](#) <> [Reply to Message](#)

Here is all the information you asked, can you please help me?

```
[root@t248 ~]# service vz stop
```

```
Stopping OpenVZ:
```

```
[ OK ]
```

```
[root@t248 ~]# lsmod
```

Module	Size	Used by
sch_ingress	2852	1
cls_u32	6308	3
sch_sfq	4480	2
sch_htb	22144	1
simfs	3612	0
vzdquota	38576	0 [permanent]
vzdev	1792	1 vzdquota
thermal	10096	0
processor	10244	1 thermal
fan	2668	0
button	4408	0
battery	7052	0
asus_acpi	8920	0
ac	3084	0
8139too	20160	0
e100	31552	0
mii	3808	2 8139too,e100
usbcore	100356	1

```
[root@t248 ~]# service vz start
```

```
Starting OpenVZ:
```

```
[ OK ]
```

```
!Bringing up interface venet0:
```

```
[ OK ]
```

```
Configuring interface venet0: net.ipv4.conf.venet0.send_redirects = 0
```

```
[ OK ]
```

```
Starting VPS 101: smod
```

```
[ OK ]
```

```
[root@t248 ~]# lsmod
```

Module	Size	Used by
vznetdev	12480	2
vzmon	41664	2 vznetdev
af_packet	16360	0
ipt_length	1504	1
ipt_ttl	1632	1
ipt_tcpmss	1920	1
ipt_TCPMSS	3648	1
iptable_mangle	4256	1
iptable_filter	4096	1
ipt_multiport	1760	1
ipt_limit	1952	1

```

ipt_tos          1408 1
ipt_REJECT       5568 1
ip_tables        20848 10 ipt_length,ipt_ttl,ipt_tcpmss,ipt_TCPMSS,iptable_mangle,iptable_filter,ipt_multiport,ipt_limit,ipt_tos,ipt_REJECT
sch_ingress      2852 1
cls_u32          6308 3
sch_sfq          4480 2
sch_htb          22144 1
simfs            3612 1
vzdquota         38576 1 [permanent]
vzdev            1792 3 vznetdev,vzmon,vzdquota
thermal          10096 0
processor        10244 1 thermal
fan              2668 0
button           4408 0
battery          7052 0
asus_acpi        8920 0
ac               3084 0
8139too          20160 0
e100             31552 0
mii              3808 2 8139too,e100
usbcore          100356 1

```

```
[root@t248 ~]# vzctl stop 101
```

```
Stopping VPS ...
```

```
VPS was stopped
```

```
VPS is unmounted
```

```
[root@t248 ~]# lsmod
```

```

Module          Size Used by
vznetdev         12480 3
vzmon            41664 2 vznetdev
af_packet        16360 0
ipt_length       1504 1
ipt_ttl          1632 1
ipt_tcpmss       1920 1
ipt_TCPMSS       3648 1
iptable_mangle   4256 1
iptable_filter   4096 1
ipt_multiport    1760 1
ipt_limit        1952 1
ipt_tos          1408 1
ipt_REJECT       5568 1
ip_tables        20848 10 ipt_length,ipt_ttl,ipt_tcpmss,ipt_TCPMSS,iptable_mangle,iptable_filter,ipt_multiport,ipt_limit,ipt_tos,ipt_REJECT
sch_ingress      2852 1
cls_u32          6308 3
sch_sfq          4480 2
sch_htb          22144 1

```

```

simfs          3612 1
vzdquota      38576 1 [permanent]
vzdev         1792 3 vznetdev,vzmon,vzdquota
thermal       10096 0
processor     10244 1 thermal
fan           2668 0
button        4408 0
battery       7052 0
asus_acpi     8920 0
ac            3084 0
8139too       20160 0
e100          31552 0
mii           3808 2 8139too,e100
usbcore       100356 1
[root@t248 ~]#

```

```
[root@t248 ~]# vzctl start 101
```

```
Starting VPS ...
```

```
VPS is mounted
```

```
Setting CPU units: 13738
```

```
File resolv.conf was modified
```

```
VPS start in progress...
```

```
[root@t248 ~]# lsmod
```

Module	Size	Used by
vznetdev	12480	5
vzmon	41664	3 vznetdev
af_packet	16360	0
ipt_length	1504	2
ipt_ttl	1632	2
ipt_tcpmss	1920	2
ipt_TCPMSS	3648	2
iptable_mangle	4256	2
iptable_filter	4096	2
ipt_multiport	1760	2
ipt_limit	1952	2
ipt_tos	1408	2
ipt_REJECT	5568	2
ip_tables	20848	10 ipt_length, ipt_ttl, ipt_tcpmss, ipt_TCPMSS, iptable_mangle, iptable_filter, ipt_multiport, ipt_limit, ipt_tos, ipt_REJECT
sch_ingress	2852	1
cls_u32	6308	3
sch_sfq	4480	2
sch_htb	22144	1
simfs	3612	2
vzdquota	38576	2 [permanent]
vzdev	1792	3 vznetdev, vzmon, vzdquota
thermal	10096	0
processor	10244	1 thermal

```
fan          2668 0
button       4408 0
battery      7052 0
asus_acpi    8920 0
ac           3084 0
8139too      20160 0
e100         31552 0
mii          3808 2 8139too,e100
usbcore      100356 1
```

```
[root@t248 ~]# cat /etc/sysconfig/vz
```

```
## Global parameters
```

```
VIRTUOZZO=yes
```

```
LOCKDIR=/vz/lock
```

```
VE0CPUUNITS=1000
```

```
## Logging parameters
```

```
LOGGING=yes
```

```
LOGFILE=/var/log/vzctl.log
```

```
LOG_LEVEL=0
```

```
## Disk quota parameters
```

```
DISK_QUOTA=yes
```

```
VZFASTBOOT=no
```

```
# The name of the device whose ip address will be used as source ip for VE.
```

```
# By default automatically assigned.
```

```
#VE_ROUTE_SRC_DEV="eth0"
```

```
## Template parameters
```

```
TEMPLATE=/vz/template
```

```
## Defaults for VEs
```

```
VE_ROOT=/vz/root/$VEID
```

```
VE_PRIVATE=/vz/private/$VEID
```

```
CONFIGFILE="vps.basic"
```

```
DEF_OSTEMPLATE="fedora-core-4"
```

```
## Load vzwdog module
```

```
VZWDOG="no"
```

```
IPTABLES="ipt_REJECT ipt_tos ipt_limit ipt_multiport iptable_filter iptable_mangle ipt_TCPMSS  
ipt_tcpmss ipt_ttl ipt_length"
```

```
[root@t248 ~]#
```

```
[root@t248 ~]# cat /etc/sysconfig/vz-scripts/101.conf
```

```
# This is an example configuration file for so-called "vps.basic" VPS.
```

```
# Copyright (C) 2000-2005 SWsoft. All rights reserved.
```

```
#
# This file may be distributed under the terms of the Q Public License
# as defined by Trolltech AS of Norway and appearing in the file
# LICENSE.QPL included in the packaging of this file.
#
# This file is provided AS IS with NO WARRANTY OF ANY KIND, INCLUDING THE
# WARRANTY OF DESIGN, MERCHANTABILITY AND FITNESS FOR A PARTICULAR
# PURPOSE.
```

```
ONBOOT="yes"
```

```
# UBC parameters (in form of barrier:limit)
```

```
# Primary parameters
```

```
AVNUMPROC="209:209"
```

```
NUMPROC="800:800"
```

```
NUMTCPSOCK="800:800"
```

```
NUMOTHERSOCK="800:800"
```

```
VMGUARPAGES="15977:2147483647"
```

```
# Secondary parameters
```

```
KMEMSIZE="5141514:8855665"
```

```
TCPSNDBUF="2437038:5713838"
```

```
TCPRCVBUF="2437038:5713838"
```

```
OTHERSOCKBUF="1218519:4495319"
```

```
DGRAMRCVBUF="1218519:1218519"
```

```
OOMGUARPAGES="15977:2147483647"
```

```
# Auxiliary parameters
```

```
LOCKEDPAGES="836:836"
```

```
SHMPAGES="9586:9586"
```

```
PRIVVMPAGES="80862:85448"
```

```
NUMFILE="6688:6688"
```

```
NUMFLOCK="668:734"
```

```
NUMPTY="80:80"
```

```
NUMSIGINFO="1024:1024"
```

```
DCACHESIZE="3740085:3852288"
```

```
PHYSPAGES="0:2147483647"
```

```
NUMIPTENT="200:200"
```

```
# Disk quota parameters (in form of softlimit:hardlimit)
```

```
DISKSPACE="20971520:22971520"
```

```
DISKINODES="2880189:2968209"
```

```
QUOTATIME="0"
```

```
# CPU fair sheduler parameter
```

```
CPUUNITS="13738"
```

```
VE_ROOT="/vz/root/$VEID"
```

```
VE_PRIVATE="/vz/private/$VEID"
```

```
OSTEMPLATE="debian-3.1-i386-minimal"
```

ORIGIN_SAMPLE="vps.10"
