
Subject: Re: Howto config ve of ram 1GB
Posted by [powervps](#) on Sat, 08 Dec 2007 00:46:07 GMT
[View Forum Message](#) <> [Reply to Message](#)

Look what iam geting sir

```
[root@vpsvps ~]# vzctl create 101 --config vps.basic --hostname server.xxx.net
Warning: VE config file already exists, will be rewritten with /etc/vz/conf/ve-vps.basic.conf-sample
Private area already exists in /vz/private/101
[root@vpsvps ~]# vzctl start 101
Warning: distribution not specified default used /etc/vz/dists/default
Starting VE ...
vzquota : (warning) block_hard_limit [1153534] < block_current_usage [2934380]
VE is mounted
Setting CPU units: 1000
Configure meminfo: 49152
vzquota : (warning) block_hard_limit [1153434] < block_current_usage [2934380]
VE start in progress...
```

Quote:

```
# Copyright (C) 2000-2007 SWsoft. All rights reserved.
#
# This program is free software; you can redistribute it and/or modify
# it under the terms of the GNU General Public License as published by
# the Free Software Foundation; either version 2 of the License, or
# (at your option) any later version.
#
# This program is distributed in the hope that it will be useful,
# but WITHOUT ANY WARRANTY; without even the implied warranty of
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
#
# You should have received a copy of the GNU General Public License
# along with this program; if not, write to the Free Software
# Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
#
```

```
ONBOOT="yes"
```

```
# UBC parameters (in form of barrier:limit)
# Primary parameters
AVNUMPROC="360"
NUMPROC="480"
NUMTCPSOCK="720:720"
NUMOTHERSOCK="720:720"
VMGUARPAGES="131072:2147483647"
```

```
# Secondary parameters
KMEMSIZE="22111846:22754099"
TCPSNDBUF="319488:524288"
TCPRCVBUF="3440640:5406720"
OTHERSOCKBUF="135168:237568"
DGRAMRCVBUF="524288:524288"
OOMGUARPAGES="1725:2147483647"
# Auxiliary parameters
LOCKEDPAGES="1024:1024"
SHMPAGES="512:512"
PRIVVMPAGES="256000:262140"
NUMFILE="18624"
NUMFLOCK="396:412"
NUMPTY="32:32"
NUMSIGINFO="512:512"
DCACHESIZE="6819840:7249920"

PHYSPAGES="0:2147483647"
NUMIPTENT="256:256"

# Disk quota parameters (in form of softlimit:hardlimit)
DISKSPACE="512000:512000"
DISKINODES="80000:88000"
QUOTATIME="0"

# CPU fair sheduler parameter
CPUUNITS="1000"
```
