Subject: Re: Netfilter connection tracking not working in VE? Posted by lst hoe01 on Thu, 06 Mar 2008 11:21:03 GMT

View Forum Message <> Reply to Message

Zitat von Frederik <freggy@gmail.com>:

```
> Hi,
> I am using Shorewall to set up a firewall in a VE. Now the problem is
> that outgoing connections do not work, although I accept traffic from the
> firewall to the network zone. I contacted the shorewall developer, and he
> took a look at my configuration and he thinks that something is going
> wrong in the kernel's connection tracking system. It seems indeed the
> incoming packets responding to the outgoing packets, do not match the
> state RELATED, ESTABLISHED rules which should accept them. Disabling the
> firewall in the VE, or creating rules which accept the incoming packets,
> makes it work, but of course this should not be necessary with the
> RELATED, ESTABLISHED rule.
>
> Some information on the hardware host (running Debian Lenny):
> http://artipc10.vub.ac.be/openvz/hnode.txt
> And on the VE (running Debian Etch):
> http://artipc10.vub.ac.be/openvz/ve.txt
> As you can see in the shorewall show output, no packets matched the
> RELATED, ESTABLISHED rule in the net2fw rule, but instead packets are
> matched by the fallback rule forwarding them to the Drop chain, and they
> eventually seem to be dropped in the DropInvalid chain because of state
> INVALID.
> There's a Shorewall firewall on the hardware host too, but that one
> accepts all relevant traffic: everything works with the firewall on the
> hardware node enabled and the firewall in the VE disabled.
>
> A related question, where can I find the logs of the firewall in the VE?
```

The available features of iptables depend on the kernel modules loaded. By default it is not possible to load additional kernel modules on demand inside the VE. Older kernels even need to enable firewall inside the VE to get it work but i don't know for which version this have changed. So double check if the necessary modules are loaded at startup and if the kernel log /proc/kmesg is available inside the VE.

> dmesg in the VE is empty and nothing is logged in /var/log, while the > logs in the hardware node only seem to reflect the firewall on the

> hardware node.

Regards

Andreas

--

All your trash belong to us ;-) www.spamschlucker.org To: stephan@spamschlucker.org