
Subject: Re: Problem using veth
Posted by [edillmann](#) on Mon, 09 Jun 2008 15:34:33 GMT
[View Forum Message](#) <> [Reply to Message](#)

HN BEFORE :

```
ip a l
1: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,LOWER_UP> mtu 1500 qdisc noqueue
  link/void
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast qlen 1000
  link/ether 00:09:6b:8c:90:7e brd ff:ff:ff:ff:ff:ff
  inet 192.168.3.203/24 brd 192.168.3.255 scope global eth0
4: eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 9000 qdisc pfifo_fast qlen 1000
  link/ether 00:09:6b:8c:90:7f brd ff:ff:ff:ff:ff:ff
  inet 192.168.254.203/24 brd 192.168.254.255 scope global eth1
6: lo: <LOOPBACK,UP,LOWER_UP> mtu 16436 qdisc noqueue
  link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
  inet 127.0.0.1/8 scope host lo
```

```
cat /proc/vz/veth
Version: 1.0
```

HN AFTER:

```
cat /proc/vz/veth
Version: 1.0
00:18:51:05:12:f4 veth167.0_ifren 00:18:51:14:f0:ef eth0 167 deny
```

```
ip a l
1: venet0: <BROADCAST,POINTOPOINT,NOARP,UP,LOWER_UP> mtu 1500 qdisc noqueue
  link/void
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast qlen 1000
  link/ether 00:09:6b:8c:90:7e brd ff:ff:ff:ff:ff:ff
  inet 192.168.3.203/24 brd 192.168.3.255 scope global eth0
4: eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 9000 qdisc pfifo_fast qlen 1000
  link/ether 00:09:6b:8c:90:7f brd ff:ff:ff:ff:ff:ff
  inet 192.168.254.203/24 brd 192.168.254.255 scope global eth1
6: lo: <LOOPBACK,UP,LOWER_UP> mtu 16436 qdisc noqueue
  link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
  inet 127.0.0.1/8 scope host lo
9: veth167.0_ifren: <BROADCAST,MULTICAST> mtu 1500 qdisc noop
  link/ether 00:18:51:05:12:f4 brd ff:ff:ff:ff:ff:ff
```

```
uname -a
Linux obsm4.example.com 2.6.18-028stab053 #2 SMP Thu Jan 31 20:48:41 CET 2008 i686
GNU/Linux
```

```
vzctl --version
```

vzctl version 3.0.22
