
Posted by [Bobele](#) on Tue, 07 Oct 2008 20:02:39 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
ovz-1:~# brctl show
bridge name bridge id STP enabled interfaces
br0 8000.00185194eec9 no eth1
                                veth301.0
```

```
ovz-1:~# vzctl restart 301
Restarting VE
Stopping VE ...
VE was stopped
VE is unmounted
Starting VE ...
VE is mounted
Setting CPU units: 1000
Configure meminfo: 232771
Set hostname: www.xxx.xx
File resolv.conf was modified
Configure veth devices: veth301.0
VE start in progress...
```

```
ovz-1:~# brctl show
bridge name bridge id STP enabled interfaces
br0 8000.00304890bf9b no eth1
```

```
ovz-1:~# vzctl exec 301 ifconfig
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        inet6 addr: ::1/128 Scope:Host
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:37 errors:0 dropped:0 overruns:0 frame:0
        TX packets:37 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:20477 (19.9 KiB)  TX bytes:20477 (19.9 KiB)
```

```
venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)
```

