Subject: Re: error /sbin/ip: 1: Syntax error: Unterminated quoted string Posted by lowlow2 on Wed, 14 Oct 2009 07:58:48 GMT

View Forum Message <> Reply to Message

ramjet wrote on Tue, 13 October 2009 17:48Some command is returning the string "vps-net_add Warning: Device list is empty" and then each word is treated as a network device.

How does your 101.conf and 201.conf files look like?

What does Is /var/lib/vz/private output?

Quote: I manually copied files to the host /var/lib/private/201

Did something go wrong with your copy command. Above command has no vz in path.

It seems you somehow have changed a globally configuration file or setting.

Thx. The command 'ls /var/lib/vz/private' returns 101 and 201; my two containers. Also the structure/content of the this two subfolders is fine.

Maybe I wasn't very clear before but what I did was: I was trying to make a sort of clone of a VE on another machine so I copied the files manually. When I saw that I got errors I decided to undo my operation. I restarted the host, destroyed the VE (succesfully) and made a new VE (id: 201). I've never touched container 101 so find it weird it doesn't start anymore. Below the 201.conf; which seems okay?

PS: the same error persists when starting both the containers

Thanks in advance

```
# Copyright (C) 2000-2007 SWsoft. All rights reserved.
#
# This program is free software; you can redistribute it and/or modify
# it under the terms of the GNU General Public License as published by
# the Free Software Foundation; either version 2 of the License, or
# (at your option) any later version.
#
# This program is distributed in the hope that it will be useful,
# but WITHOUT ANY WARRANTY; without even the implied warranty of
# MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
# GNU General Public License for more details.
#
# You should have received a copy of the GNU General Public License
# along with this program; if not, write to the Free Software
# Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA
#
```

ONBOOT="yes"

UBC parameters (in form of barrier:limit)

KMEMSIZE="11055923:11377049"

LOCKEDPAGES="256:256"

PRIVVMPAGES="65536:69632"

SHMPAGES="21504:21504"

NUMPROC="240:240"

PHYSPAGES="0:2147483647"

VMGUARPAGES="33792:2147483647"

OOMGUARPAGES="26112:2147483647"

NUMTCPSOCK="360:360"

NUMFLOCK="188:206"

NUMPTY="16:16"

NUMSIGINFO="256:256"

TCPSNDBUF="1720320:2703360"

TCPRCVBUF="1720320:2703360"

OTHERSOCKBUF="1126080:2097152"

DGRAMRCVBUF="262144:262144"

NUMOTHERSOCK="120:120"

DCACHESIZE="3409920:3624960"

NUMFILE="9312:9312"

AVNUMPROC="180:180"

NUMIPTENT="128:128"

Disk quota parameters (in form of softlimit:hardlimit)

DISKSPACE="1048576:1153024"

DISKINODES="200000:220000"

QUOTATIME="0"

CPU fair sheduler parameter

CPUUNITS="1000"

VE_ROOT="/var/lib/vz/root/\$VEID"

VE_PRIVATE="/var/lib/vz/private/\$VEID"

OSTEMPLATE="ubuntu-8.04-x86"

ORIGIN_SAMPLE="vps.basic"

NAMESERVER="192.168.0.2 192.168.0.3"

HOSTNAME="wiki.ixx.iyy.be"

IP ADDRESS="192.168.0.233"