
Subject: Very Weird Problem. sometimes VE starts perfect other times it does not
Posted by [michaelv](#) on Tue, 25 May 2010 08:27:57 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi OpenVz...

I have a very special problem and I hope one person might have seen the same issue... I have this problem posted on the proxmox forum but no reply so far... So this is what I have posted...

Hi Proxmox.

I have spent a couple of days to make my own shell script which does what this guide is promising. http://wiki.openvz.org/Physical_to_container

I have one problem now which I really can not solve.

When I restart the Container it sometimes doesn't bring up its networking properly which of course means I can not access the server at all.

When I try to check the network status with a `ifconfig` the command doesn't show anything at all..

I have a dump of the `init.log` when it's okay and when it fails...

Any clue what is wrong ????

```
pveversion -v
pve-manager: 1.5-9 (pve-manager/1.5/4728)
running kernel: 2.6.24-10-pve
proxmox-ve-2.6.24: 1.5-21
pve-kernel-2.6.24-10-pve: 2.6.24-21
pve-kernel-2.6.24-8-pve: 2.6.24-16
qemu-server: 1.1-14
pve-firmware: 1.0-5
libpve-storage-perl: 1.0-13
vncterm: 0.9-2
vzctl: 3.0.23-1pve11
vzdump: 1.2-5
vzprocps: 2.0.11-1dso2
vzquota: 3.0.11-1
pve-qemu-kvm: 0.12.4-1
:/# uname -a
Linux xxxxxxxxx 2.6.24-10-pve #1 SMP PREEMPT Tue Dec 29 10:16:15 CET 2009 x86_64
GNU/Linux
```

Thanks.

/Michael

----- ok /var/log/init.log -----

starting init logger

INIT: version 2.86 booting

/etc/rc.d/rc.sysinit: line 232: /dev/tty1: Permission denied

Welcome to CentOS release 5 (Final)

Press 'I' to enter interactive startup.

Cannot access the Hardware Clock via any known method.

Use the --debug option to see the details of our search for an access method.

Setting clock (utc): Fri May 21 11:51:29 CEST 2010 [OK]

Loading default keymap (dk): /etc/rc.d/rc.sysinit: line 388: /dev/tty0: Permissi on denied
[FAILED]

Setting hostname new: [OK]

raidautorun: failed to open /dev/md0: Permission denied

awk: cmd. line:1: fatal: cannot open file `/proc/misc' for reading (No such file or directory)

Remounting root filesystem in read-write mode: mount: permission denied
[FAILED]

Mounting local filesystems: mount: sysfs already mounted or /sys busy

mount: according to mtab, /sys is already mounted on /sys

[FAILED]

Enabling local filesystem quotas: [OK]

/etc/rc.d/rc.sysinit: line 756: /dev/urandom: Permission denied

Enabling /etc/fstab swaps: [OK]

INIT: Entering runlevel: 3

Entering non-interactive startup

Applying Intel CPU microcode update: FATAL: Could not load /lib/modules/2.6.24-1

0-pve/modules.dep: No such file or directory

/etc/rc3.d/S00microcode_ctl: microcode device /dev/cpu/microcode doesn't exist?

Starting background readahead: [OK]

Bringing up loopback interface: [OK]

Bringing up interface venet0: SIOCADDRT: No such process

[OK]

Starting auditd: [FAILED]

Starting irqbalance: [OK]

Starting RPC idmapd: FATAL: Could not load /lib/modules/2.6.24-10-pve/modules.de p: No such
file or directory

Error: RPC MTAB does not exist.

Starting PC/SC smart card daemon (pcscd): [OK]

Starting sshd:WARNING: initlog is deprecated and will be removed in a future rel ease
[OK]

----- failed /var/log/init.log -----

starting init logger

INIT: version 2.86 booting

/etc/rc.d/rc.sysinit: line 232: /dev/tty1: Permission denied

Welcome to CentOS release 5 (Final)

Press 'I' to enter interactive startup.
Cannot access the Hardware Clock via any known method.
Use the --debug option to see the details of our search for an access method.
Setting clock (utc): Fri May 21 12:06:50 CEST 2010 [OK]
Loading default keymap (dk): /etc/rc.d/rc.sysinit: line 388: /dev/tty0: Permission denied
[FAILED]
Setting hostname new: [OK]
raidautorun: failed to open /dev/md0: Permission denied
awk: cmd. line:1: fatal: cannot open file `/proc/misc' for reading (No such file or directory)
Remounting root filesystem in read-write mode: mount: permission denied
[FAILED]
Mounting local filesystems: mount: sysfs already mounted or /sys busy
mount: according to mtab, /sys is already mounted on /sys
[FAILED]
Enabling local filesystem quotas: [OK]
/etc/rc.d/rc.sysinit: line 756: /dev/urandom: Permission denied
ng /etc/fstab swaps: [OK]
INIT: Entering runlevel: 3
Entering interactive startup
Start service microcode_ctl (Y)es/(N)o/(C)ontinue? [Y]
