
Subject: Re: debian veth0 is always 127.0.0.1
Posted by [disaster](#) on Tue, 25 Jul 2006 17:50:05 GMT
[View Forum Message](#) <> [Reply to Message](#)

For me it is:

```
lo      Link encap:Local Loopback
        inet addr:127.0.0.1  Mask:255.0.0.0
        UP LOOPBACK RUNNING  MTU:16436  Metric:1
        RX packets:0 errors:0 dropped:0 overruns:0 frame:0
        TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:0 (0.0 b)  TX bytes:0 (0.0 b)

venet0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        inet addr:127.0.0.1  P-t-P:127.0.0.1  Bcast:0.0.0.0  Mask:255.255.255.255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:1
        RX packets:8267 errors:0 dropped:0 overruns:0 frame:0
        TX packets:6600 errors:0 dropped:0 overruns:0 carrier:0
        collisions:0 txqueuelen:0
        RX bytes:5673417 (5.4 MiB)  TX bytes:1561875 (1.4 MiB)

venet0:0  Link encap:UNSPEC  HWaddr 00-00-00-00-00-00-00-00-00-00-00-00-00-00-00-00
        inet addr:85.158.178.11  P-t-P:85.158.178.11  Bcast:0.0.0.0  Mask:255.255.255.255
        UP BROADCAST POINTOPOINT RUNNING NOARP  MTU:1500  Metric:
```

and the auto generated /etc/network/interfaces is:

```
# Auto generated venet0 interfaces
auto venet0 lo
iface venet0 inet static
    address 127.0.0.1
    netmask 255.255.255.255
    broadcast 0.0.0.0
    up route add -net 191.255.255.1 netmask 255.255.255.255 dev venet0
    up route add default gw 191.255.255.1
iface lo inet loopback

auto venet0:0
iface venet0:0 inet static
    address 85.158.178.11
    netmask 255.255.255.255
    broadcast 0.0.0.0
```
