
Subject: Re: Broken VPS problem

Posted by [ferp2](#) on Thu, 05 Oct 2006 17:30:46 GMT

[View Forum Message](#) <> [Reply to Message](#)

I ran strace again using the following parameters:

```
strace -o strace.out -ff vzctl status 101
execve("/usr/sbin/vzctl", ["vzctl", "status", "101"], [/* 17 vars */]) = 0
uname({sys="Linux", node="cveil", ...}) = 0
brk(0)                                = 0x8050000
old_mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1,
0) = 0x40017000
access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
open("/etc/ld.so.preload", O_RDONLY)  = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/i686/mmx/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such
file or directory)
stat64("/usr/lib/vzctl/lib/tls/i686/mmx/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/i686/mmx/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/i686/mmx", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/i686/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/i686/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/i686/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/i686", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/mmx/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/mmx/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/mmx/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/mmx", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/tls/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/tls/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or directory)
stat64("/usr/lib/vzctl/lib/tls", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/i686/mmx/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file
or directory)
stat64("/usr/lib/vzctl/lib/i686/mmx/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/i686/mmx/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/i686/mmx", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/i686/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/i686/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/i686/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or directory)
stat64("/usr/lib/vzctl/lib/i686", 0xbffff298) = -1 ENOENT (No such file or directory)
```

```

open("/usr/lib/vzctl/lib/mmx/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/mmx/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/mmx/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/mmx", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/cmov/libvzctl.so.0.0.2", O_RDONLY) = -1 ENOENT (No such file or
directory)
stat64("/usr/lib/vzctl/lib/cmov", 0xbffff298) = -1 ENOENT (No such file or directory)
open("/usr/lib/vzctl/lib/libvzctl.so.0.0.2", O_RDONLY) = 3
read(3, "\177ELF\1\1\1\0\0\0\0\0\0\0\0\3\0\3\0\1\0\0\0`K\0\000"..., 512) = 512
fstat64(3, {st_mode=S_IFREG|0644, st_size=144408, ...}) = 0
old_mmap(NULL, 143328, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x40018000
old_mmap(0x4003a000, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3,
0x22000) = 0x4003a000
close(3) = 0
open("/usr/lib/vzctl/lib/libvzctl-simfs.so.0.0.2", O_RDONLY) = 3
read(3, "\177ELF\1\1\1\0\0\0\0\0\0\0\0\3\0\3\0\1\0\0\0\0\0\0\0\000"..., 512) = 512
fstat64(3, {st_mode=S_IFREG|0644, st_size=6488, ...}) = 0
old_mmap(NULL, 9548, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x4003b000
old_mmap(0x4003d000, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3,
0x1000) = 0x4003d000
close(3) = 0
open("/usr/lib/vzctl/lib/libdl.so.2", O_RDONLY) = -1 ENOENT (No such file or directory)
open("/etc/ld.so.cache", O_RDONLY) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=11552, ...}) = 0
old_mmap(NULL, 11552, PROT_READ, MAP_PRIVATE, 3, 0) = 0x4003e000
close(3) = 0
access("/etc/ld.so.nohwcap", F_OK) = -1 ENOENT (No such file or directory)
open("/lib/tls/libdl.so.2", O_RDONLY) = 3
read(3, "\177ELF\1\1\1\0\0\0\0\0\0\0\0\3\0\3\0\1\0\0\0\320\32"..., 512) = 512
fstat64(3, {st_mode=S_IFREG|0644, st_size=9872, ...}) = 0
old_mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1,
0) = 0x40041000
old_mmap(NULL, 8632, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x40042000
old_mmap(0x40044000, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3,
0x2000) = 0x40044000
close(3) = 0
open("/usr/lib/vzctl/lib/libutil.so.1", O_RDONLY) = -1 ENOENT (No such file or directory)
access("/etc/ld.so.nohwcap", F_OK) = -1 ENOENT (No such file or directory)
open("/lib/tls/libutil.so.1", O_RDONLY) = 3
read(3, "\177ELF\1\1\1\0\0\0\0\0\0\0\0\3\0\3\0\1\0\0\0000\16\0"..., 512) = 512
fstat64(3, {st_mode=S_IFREG|0644, st_size=7828, ...}) = 0
old_mmap(NULL, 10652, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x40045000
old_mmap(0x40047000, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3,
0x1000) = 0x40047000
close(3) = 0
open("/usr/lib/vzctl/lib/libc.so.6", O_RDONLY) = -1 ENOENT (No such file or directory)

```

```

access("/etc/ld.so.nohwcap", F_OK)    = -1 ENOENT (No such file or directory)
open("/lib/tls/libc.so.6", O_RDONLY)  = 3
read(3, "\177ELF\1\1\1\0\0\0\0\0\0\0\0\0\0\3\0\1\0\0\0\0Z\1\000"..., 512) = 512
fstat64(3, {st_mode=S_IFREG|0755, st_size=1254660, ...}) = 0
old_mmap(NULL, 1264972, PROT_READ|PROT_EXEC, MAP_PRIVATE, 3, 0) = 0x40048000
old_mmap(0x40172000, 36864, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED, 3, 0x129000) = 0x40172000
old_mmap(0x4017b000, 7500, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_FIXED|MAP_ANONYMOUS, -1, 0) = 0x4017b000
close(3)                                = 0
old_mmap(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x4017d000
set_thread_area({entry_number:-1 -> 6, base_addr:0x4017d080, limit:1048575, seg_32bit:1, contents:0, read_exec_only:0, limit_in_pages:1, seg_not_present:0, useable:1}) = 0
munmap(0x4003e000, 11552)               = 0
brk(0)                                  = 0x8050000
brk(0x8071000)                          = 0x8071000
brk(0)                                  = 0x8071000
rt_sigaction(SIGPIPE, {SIG_IGN}, NULL, 8) = 0
open("/etc/vz/vz.conf", O_RDONLY)       = 3
stat64("/etc/vz/vz.conf", {st_mode=S_IFREG|0644, st_size=764, ...}) = 0
fstat64(3, {st_mode=S_IFREG|0644, st_size=764, ...}) = 0
mmap2(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x4003e000
read(3, "## Global parameters\n#\nVIRTUOZZO"..., 4096) = 764
read(3, "", 4096)                       = 0
close(3)                                = 0
munmap(0x4003e000, 4096)                = 0
open("/var/log/vzctl.log", O_WRONLY|O_APPEND|O_CREAT, 0666) = 3
fstat64(3, {st_mode=S_IFREG|0644, st_size=583260, ...}) = 0
mmap2(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x4003e000
fstat64(3, {st_mode=S_IFREG|0644, st_size=583260, ...}) = 0
_llseek(3, 583260, [583260], SEEK_SET) = 0
stat64("/etc/vz/conf//101.conf", 0xbffff7c4) = -1 ENOENT (No such file or directory)
fcntl64(0, F_GETFL)                     = 0x8002 (flags O_RDWR|O_LARGEFILE)
fcntl64(1, F_GETFL)                     = 0x8002 (flags O_RDWR|O_LARGEFILE)
fcntl64(2, F_GETFL)                     = 0x8002 (flags O_RDWR|O_LARGEFILE)
open("/dev/vzctl", O_RDWR)               = 4
ioctl(4, 0x400c2e05, 0xbffff5b0)        = 0
stat64("/var/lib/vz/private/101", 0xbffff294) = -1 ENOENT (No such file or directory)
open("/proc/mounts", O_RDONLY)           = 5
fstat64(5, {st_mode=S_IFREG|0444, st_size=0, ...}) = 0
mmap2(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) = 0x4003f000
read(5, "/dev/root.old /initrd cramfs ro "..., 1024) = 352
read(5, "", 1024)                       = 0
close(5)                                = 0

```

```
munmap(0x4003f000, 4096)          = 0
ioctl(4, 0x400c2e05, 0xbffff370) = -1 ESRCH (No such process)
fstat64(1, {st_mode=S_IFCHR|0620, st_rdev=makedev(136, 0), ...}) = 0
mmap2(NULL, 4096, PROT_READ|PROT_WRITE, MAP_PRIVATE|MAP_ANONYMOUS, -1, 0) =
0x4003f000
write(1, "VPSID 101 deleted unmounted down"..., 33) = 33
close(4)                          = 0
close(3)                          = 0
munmap(0x4003e000, 4096)          = 0
munmap(0x4003f000, 4096)          = 0
exit_group(0)                     = ?
```
