

---

Subject: Re: Re: template Gentoo, Init  
Posted by [Tonko Mulder](#) on Fri, 06 Oct 2006 18:11:10 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hello Kir,  
I am not the owner of the host system :)  
I had debian succesfully installed using debootstrap..  
the idea is to do the same with gentoo..

This is part of a dutch project to test out virtual servers from  
Strato, germany.

I made a little bash script which puts the output of 'ps -ax' in  
/root/firstboot..

This has the following content:

---

```
USER      PID %CPU %MEM    VSZ   RSS TTY      STAT START   TIME COMMAND
root         1  0.0  0.0  1396  488 ?        Ss   16:31   0:00 init
root    3497  4.6  0.0  2384 1396 ?        Ss   16:40   0:00
/bin/bash /sbin/rc shutdown
root    4423  0.0  0.0  2524 1428 ?        S    16:40   0:00
/bin/bash /sbin/rc shutdown
root    4431  0.0  0.0  2032  852 ?        R    16:40   0:00 ps -aux
```

```
USER      PID %CPU %MEM    VSZ   RSS TTY      STAT START   TIME COMMAND
root         1  0.0  0.0  1396  488 ?        Ss   16:31   0:00 init
root    3497  4.6  0.0  2384 1396 ?        Ss   16:40   0:00
/bin/bash /sbin/rc shutdown
root    4423  0.0  0.0  2524 1428 ?        S    16:40   0:00
/bin/bash /sbin/rc shutdown
root    4433  0.0  0.0  2032  852 ?        R    16:40   0:00 ps -aux
```

--

Just to give you an idea :)  
I would like to know why and where shutdown gets initiated.. so I can  
stop it and let the VPS boot normal..

Tonko

On 10/6/06, Kir Kolyshkin <[kir@openvz.org](mailto:kir@openvz.org)> wrote:

```
> 1. This is not Virtuozzo support. If you are Virtuozzo customer, ask
> their support. If you are hosting customer -- ask you HSP support.
>
> 2. Steps of modifying a new Gentoo installation to adopt it to OpenVZ
> are described at http://wiki.openvz.org/Gentoo\_template\_creation
> (starting from the item #5). I can not guarantee they are applicable to
> Virtuozzo.
>
> Tonko Mulder wrote:
> > It was already set to 'no'..
```

> > setting it to 'yes' didn't make any difference  
> >  
> >>> Hi,  
> >  
> >>> Tonko Mulder wrote:  
> >> Hello all,  
> >>  
> >> I have the gentoo template running on a virtuoizzo server..  
> >> Only I have the following problem, every time I want to boot my  
> >> virtual machine it goes to init 0..  
> >> the init gets it's commands from inittab, but I don't know exactly if  
> >> that should be adapted for a virtual machine..  
> >>> Try adapting RC\_PARALLEL\_STARTUP="no" in /etc/conf.d/rc. This makes  
> >>> sometimes problems ;)  
> >>  
> >> regards  
> >>> Regards,  
> >>> Martin  
> >  
> > On 10/2/06, Tonko Mulder <tonko.mulder@gmail.com> wrote:  
> >> Hello all,  
> >>  
> >> I have the gentoo template running on a virtuoizzo server..  
> >> Only I have the following problem, every time I want to boot my  
> >> virtual machine it goes to init 0..  
> >> the init gets it's commands from inittab, but I don't know exactly if  
> >> that should be adapted for a virtual machine..  
> >>  
> >> regards  
> >> --  
> >> Tonko  
> >>  
> >  
> >  
>  
>  
--  
Tonko

---