
Subject: Re: Separate logfile and console loglevel
Posted by [kfh](#) on Tue, 05 Dec 2006 12:07:59 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Tuesday den 5. December 2006 12:40, Igor Sukhih wrote:

> > On Tuesday den 5. December 2006 11:47, Igor Sukhih wrote:

> >>> On Thursday den 30. November 2006 14:59, Dmitry Mishin wrote:

> >>>> Separate logfile and console loglevel

> >>>> The separation is implemented as follows

> >>>>

> >>>> 1: split --quite and --verbose from LOG_LEVEL

> >>>> console loglevel is 0 as default

> >>>>

> >>>> This patch make sense.

> >>>>

> >>>> I worked on the patch, made --verbose accept argument (--verbose=<int>)

> >>>> Added new parameter VERBOSE=<int> to /etc/vz/vz.conf. Default is 1 if

> >>>> unset. --verbose alone increments by 1

> >>>>

> >>>> 2: Make messages more quiet by default

> >>>> logger(0,...) -> logger(1, ...)

> >>>>

> >>>> 3: Make logfile more verbose by default

> >>>> LOG_LEVEL=2

> >>>>

> >>>> Why do you need them? For me, it is convinient to see at the VE start,

> >>>> which IP it has. It is better, than additional `vzlist` later.

> >>>>

> >>>> If I use a script to start 10 VEs, it would be nice to see only partial

> >>>> info. I could do that with --verbose=0. If one fails I can use

> >>>> --verbose=2 What do you think about the output below?

> >>>>

> >>>> I'm Ok with it the only problem the --verbose option already released

> >>>> and this is can break already worked scripts.

> >>>>

> >>>> --verbose still works. It increments current verbose by 1.

> >>>> If I run:

> >>>> vzctl --verbose=0 --verbose --verbose start 1010

> >>>> verbose will be 2 (0 + 1 + 1)

> >>>>

> >>>> If I correctly understand you will process --verbose and --verbose=0

> >>>> the same way?

> >>>> So 'vzctl --verbose ' will work as well?

Yes it will.

If /etc/vz/vz.conf contains VERBOSE=1 (or no VERBOSE at all)
vzctl --verbose ..., will result in verbose level 2

If /etc/vz/vz.conf contains VERBOSE=0, the command:
vzctl --verbose ..., will result in verbose level 1

If /etc/vz/vz.conf contains VERBOSE=2, the command:
vzctl --verbose=0 --verbose ..., will result in verbose level 1,
as VERBOSE is ignored if commandline contains --verbose="number"

<Stupid example>

/etc/vz/vz.conf contains VERBOSE=99

vzctl --verbose --verbose=1 --verbose --verbose ...

verbose=99, +1, verbose=1, +1, +1. The resulting verbose will be 3:

</Stupid example>

/Kristian.
