
Subject: Re: wtmp growth abnormal?

Posted by [jubo](#) on Fri, 22 Dec 2006 08:57:05 GMT

[View Forum Message](#) <> [Reply to Message](#)

Not that I know of. I use the VEs all day long and they aren't rebooting AFAIK. Could this have to do with the inittab or something. What else could be causing it?

Here is what it looks like.

```
# Default runlevel.
```

```
id:3:initdefault:
```

```
# System initialization, mount local filesystems, etc.
```

```
si::sysinit:/sbin/rc sysinit
```

```
# Further system initialization, brings up the boot runlevel.
```

```
rc::bootwait:/sbin/rc boot
```

```
l0:0:wait:/sbin/rc shutdown
```

```
l1:S1:wait:/sbin/rc single
```

```
l2:2:wait:/sbin/rc nonetwork
```

```
l3:3:wait:/sbin/rc default
```

```
l4:4:wait:/sbin/rc default
```

```
l5:5:wait:/sbin/rc default
```

```
l6:6:wait:/sbin/rc reboot
```

```
#z6:6:respawn:/sbin/sulogin
```

```
# TERMINALS
```

```
c1:12345:respawn:/sbin/agetty 38400 tty1 linux
```

```
c2:2345:respawn:/sbin/agetty 38400 tty2 linux
```

```
c3:2345:respawn:/sbin/agetty 38400 tty3 linux
```

```
c4:2345:respawn:/sbin/agetty 38400 tty4 linux
```

```
c5:2345:respawn:/sbin/agetty 38400 tty5 linux
```

```
c6:2345:respawn:/sbin/agetty 38400 tty6 linux
```

```
# SERIAL CONSOLES
```

```
#s0:12345:respawn:/sbin/agetty 9600 ttyS0 vt100
```

```
#s1:12345:respawn:/sbin/agetty 9600 ttyS1 vt100
```

```
# What to do at the "Three Finger Salute".
```

```
ca:12345:ctrlaltdel:/sbin/shutdown -r now
```

```
# Used by /etc/init.d/xdm to control DM startup.
```

```
# Read the comments in /etc/init.d/xdm for more
```

```
# info. Do NOT remove, as this will start nothing
```

```
# extra at boot if /etc/init.d/xdm is not added
```

```
# to the "default" runlevel.
```

x:a:once:/etc/X11/startDM.sh
