Subject: *SOLVED* vzquota: (error) Quota is not running for id 533 Posted by [QT]bender on Tue, 03 Oct 2006 07:33:56 GMT

View Forum Message <> Reply to Message

We have expirienced problem with creating VPS on our server with following configuration:

Host: Linux 2.6.16-026test018.1 i686 (Development OpenVZ Kernel)

VPS: Linux 2.6.17-1.2142_FC4smp

vzctl create 533

Creating VPS private area: /vz/private/533

vzquota: (error) Quota on syscall for 533: File exists

vzquota on failed [3]

vzquota: (error) Quota is not running for id 533

Performing postcreate actions VPS private area was created

Any ideas?

Subject: Re: vzquota : (error) Quota is not running for id 533 Posted by Vasily Tarasov on Tue, 03 Oct 2006 07:37:13 GMT

View Forum Message <> Reply to Message

Is /vz distinguished filesystem or it's just a directory in /? Do you use usual not openVZ quota on /vz (/) filesystem?

Thanks!

Subject: Re: vzquota: (error) Quota is not running for id 533 Posted by [QT]bender on Tue, 03 Oct 2006 07:49:48 GMT

View Forum Message <> Reply to Message

vass wrote on Tue, 03 October 2006 03:37ls /vz distinguished filesystem or it's just a directory in /?

Do you use usual not openVZ quota on /vz (/) filesystem?

Thanks!

/vz is just a directory.

Yes, there was a quota for /, we disabled it, but there is another error:

vzctl start 532

Starting VPS ...

VPS is mounted

Setting CPU units: 1000

vzquota: (warning) block_hard_limit [0] < block_current_usage [4]

VPS start in progress...

VPS started ok, but I'm not sure that this error message is harmless...

Subject: Re: vzquota: (error) Quota is not running for id 533 Posted by Vasily Tarasov on Tue, 03 Oct 2006 07:58:35 GMT View Forum Message <> Reply to Message

This message means that current usage of disk blocks for VE is greater than limit for it. Just increase limit.

Subject: Re: vzguota: (error) Quota is not running for id 533 Posted by [QT]bender on Tue, 03 Oct 2006 09:51:23 GMT View Forum Message <> Reply to Message

vass wrote on Tue, 03 October 2006 03:58This message means that current usage of disk blocks for VE is greater than limit for it. Just increase limit.

Thanks for your reply!