

---

Subject: VE default route

Posted by [enpx](#) on Tue, 24 Oct 2006 12:34:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

```
[root@m1 ~]# vzctl create 104 --ostemplate altlinux-sisyphus --config vps.basic
Creating VE private area: /var/lib/vz/private/104
Performing postcreate actions
VE private area was created
[root@m1 ~]# vzctl start 104
Starting VE ...
VE is mounted
Setting CPU units: 1000
VE start in progress...
[root@m1 ~]# vzctl exec 104 ip a
1: lo: <LOOPBACK> mtu 16436 qdisc noop
   link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
3: venet0: <BROADCAST,POINTOPOINT,NOARP> mtu 1500 qdisc noop
   link/void
[root@m1 ~]# vzctl exec 104 ip r
[root@m1 ~]# vzctl set 104 --veth_add veth4,00:12:34:56:78:0A,eth0,00:12:34:56:78:0B --save
Processing veth devices
Saved parameters for VE 104
[root@m1 ~]# vzctl exec 104 ip a
1: lo: <LOOPBACK,UP> mtu 16436 qdisc noqueue
   link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
   inet 127.0.0.1/8 scope host lo
   inet6 ::1/128 scope host
       valid_lft forever preferred_lft forever
3: venet0: <BROADCAST,POINTOPOINT,NOARP,UP> mtu 1500 qdisc noqueue
   link/void
   inet 127.0.0.1/32 scope host venet0
5: eth0: <BROADCAST,MULTICAST> mtu 1500 qdisc noop
   link/ether 00:12:34:56:78:0b brd ff:ff:ff:ff:ff:ff
[root@m1 ~]# vzctl exec 104 ip r
192.0.2.0/24 dev venet0 scope host
default via 192.0.2.1 dev venet0
```

---

Subject: Re: VE default route

Posted by [Andrey Mirkin](#) on Tue, 24 Oct 2006 15:23:44 GMT

[View Forum Message](#) <> [Reply to Message](#)

---