
Subject: VE default route

Posted by [enpx](#) on Tue, 24 Oct 2006 12:34:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

```
[root@m1 ~]# vzctl create 104 --ostemplate altlinux-sisyphus --config vps.basic
```

```
Creating VE private area: /var/lib/vz/private/104
```

```
Performing postcreate actions
```

```
VE private area was created
```

```
[root@m1 ~]# vzctl start 104
```

```
Starting VE ...
```

```
VE is mounted
```

```
Setting CPU units: 1000
```

```
VE start in progress...
```

```
[root@m1 ~]# vzctl exec 104 ip a
```

```
1: lo: <LOOPBACK> mtu 16436 qdisc noop
```

```
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
```

```
3: venet0: <BROADCAST,POINTOPOINT,NOARP> mtu 1500 qdisc noop
```

```
    link/void
```

```
[root@m1 ~]# vzctl exec 104 ip r
```

```
[root@m1 ~]# vzctl set 104 --veth_add veth4,00:12:34:56:78:0A,eth0,00:12:34:56:78:0B --save
```

```
Processing veth devices
```

```
Saved parameters for VE 104
```

```
[root@m1 ~]# vzctl exec 104 ip a
```

```
1: lo: <LOOPBACK,UP> mtu 16436 qdisc noqueue
```

```
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
```

```
    inet 127.0.0.1/8 scope host lo
```

```
    inet6 ::1/128 scope host
```

```
        valid_lft forever preferred_lft forever
```

```
3: venet0: <BROADCAST,POINTOPOINT,NOARP,UP> mtu 1500 qdisc noqueue
```

```
    link/void
```

```
    inet 127.0.0.1/32 scope host venet0
```

```
5: eth0: <BROADCAST,MULTICAST> mtu 1500 qdisc noop
```

```
    link/ether 00:12:34:56:78:0b brd ff:ff:ff:ff:ff:ff
```

```
[root@m1 ~]# vzctl exec 104 ip r
```

```
192.0.2.0/24 dev venet0 scope host
```

```
default via 192.0.2.1 dev venet0
```

Subject: Re: VE default route

Posted by [Andrey Mirkin](#) on Tue, 24 Oct 2006 15:23:44 GMT

[View Forum Message](#) <> [Reply to Message](#)
